




# Dimensions CM

Software version: 14.7

## Windows Installation Guide



Copyright © 2023 Open Text.

The only warranties for products and services of Open Text and its affiliates and licensors ("Open Text") are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Open Text shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Product version: 14.7

Last updated: December 8, 2023

# Table of Contents

---

<i>Chapter 1</i>	<b>Getting Started . . . . .</b>	<b>11</b>
	Supported Platforms and Integrations . . . . .	12
	Licensing with APLS . . . . .	12
	General Information . . . . .	12
	Logging Pre-Installation Information . . . . .	13
	Server . . . . .	13
	SSO and Smart Card . . . . .	14
	Useful Information . . . . .	14
	Default Installation Locations. . . . .	14
	Clients . . . . .	15
	Agents . . . . .	15
	OpenText PulseUno . . . . .	16
	CM Bridge . . . . .	16
<i>Chapter 2</i>	<b>Migrating from Serena Runtime to PostgreSQL . .</b>	<b>17</b>
	Installing your own PostgreSQL . . . . .	18
	Migration Steps . . . . .	18
<i>Chapter 3</i>	<b>Pre-Installation Tasks . . . . .</b>	<b>21</b>
	Prerequisites . . . . .	22
	Server and Agent . . . . .	22
	Installing on the Same Machine . . . . .	22
	Checking the Database is Active. . . . .	22
	Creating an Administrator Account . . . . .	23
	Choosing a Process Model . . . . .	23
	Adding Database Process Models . . . . .	24
	TCP/IP Port Usage . . . . .	25
	NTFS File System for Server Binaries . . . . .	25
	SMTP Server Details . . . . .	25
	Multiple Oracle Homes . . . . .	26
	Remote UNIX Agents and Clients . . . . .	26

Open Motif Package on Linux Agent . . . . .	26
Security on Red Hat Enterprise Linux . . . . .	26
Windows Clients . . . . .	27
SSO and Smart Card Authentication . . . . .	28
Existing SSO Server Prerequisites . . . . .	28
Smart Card Prerequisites . . . . .	29
New SSO Server Prerequisites . . . . .	30
Smart Card Client Prerequisites . . . . .	32
Networking Tasks . . . . .	33
Network Nodes Types . . . . .	33
Optimizing Network Performance . . . . .	33
Network Disk Distribution . . . . .	33
Item Library Host Performance . . . . .	35
Integrations . . . . .	35
Eclipse . . . . .	35
Visual Studio . . . . .	36
Dimensions CM Connect for SBM . . . . .	36
Closing the Microsoft Management Console . . . . .	38

## Chapter 4

<b>Preparing a Database . . . . .</b>	<b>39</b>
Introduction . . . . .	40
Preparing an Oracle Database . . . . .	41
Local Oracle Enterprise . . . . .	41
Remote Oracle Enterprise . . . . .	47
Preparing an SQL Server . . . . .	49
SQL Server Version . . . . .	49
SQL Server Collation Restrictions . . . . .	49
Preparing Local and Remote Nodes . . . . .	50
Configuring a Local Server for Remote SQL . . . . .	53
SQL Server Enterprise Roles . . . . .	54
Removing Oracle Registry Keys . . . . .	55
Oracle Multi-Byte Character Sets . . . . .	55
Oracle Database Character Set . . . . .	55
Homogeneous Server-Client Environment . . . . .	55
Preparing a PostgreSQL Database . . . . .	56
Managing Large Objects . . . . .	56
Preparing a Local PostgreSQL . . . . .	56
Preparing a Remote PostgreSQL . . . . .	56

---

	Scaling and Performance Tuning . . . . .	57
	High Availability and Load Balancing . . . . .	58
<i>Chapter 5</i>	<b>Installing Dimensions CM. . . . .</b>	<b>59</b>
	Installation Options. . . . .	60
	Running the Installer. . . . .	61
	Running the Installer from a DVD. . . . .	61
	Running the Installer from a Download . . . . .	61
	Installing all Server Components . . . . .	62
	Remote Schema Requirements . . . . .	62
	Installing a Database Remotely on Another Platform . .	63
	SSO and Smart Card Limitations . . . . .	63
	Installing a Server with a PostgreSQL Database . . . . .	63
	Installing a Server with an Oracle Database . . . . .	67
	Installing a Server with an SQL Database . . . . .	71
	Installing a Windows Server Only . . . . .	75
	Overview. . . . .	75
	Installing a Server Only . . . . .	76
	Installing an SSO Server and Smart Card . . . . .	78
	SSO and Smart Card Limitations and Requirements . . .	78
	Installing SSO and Smart Card . . . . .	78
	Fixing Demo Certificate Mismatches . . . . .	79
	Installing a Windows Agent . . . . .	80
	Installing an Agent . . . . .	80
	Checking the Agent Installation . . . . .	81
	Starting the Listener. . . . .	81
	Installing a Windows Client . . . . .	82
	Overview. . . . .	82
	Installing a Client . . . . .	83
	Checking the Client Installation . . . . .	84
	Silently Installing Windows Agents and Clients . . . . .	84
	Silently Installing OpenText Common Tools . . . . .	84
	Silently Installing Clients . . . . .	85
	Silently Installing the Shell Extension on 64-bit Windows	90
	Silently Installing an Agent . . . . .	90
	Installing Dimensions CM Make for Windows . . . . .	91
	Introduction . . . . .	91
	Downloading the Installer . . . . .	91

---

Pre-Installation Requirements . . . . .	92
Installing Make . . . . .	92
Installing the Eclipse Integration . . . . .	92
Installing the Integration from a Server . . . . .	92
Manually Installing the Integration . . . . .	93
Silently Installing the Integration . . . . .	94
Installing Other Integrations . . . . .	95

## Chapter 6

<b>Post-Installation Tasks . . . . .</b>	<b>97</b>
Server Post-Installation Tasks . . . . .	98
Checking a Server Installation . . . . .	98
Checking a Database Installation . . . . .	99
Starting a Server in Restricted Mode . . . . .	100
Licensing Dimensions CM . . . . .	101
Registering Base Databases . . . . .	101
Database Administration Acceptance Tests . . . . .	101
Command-Line Acceptance Tests . . . . .	101
Multi-Homed Servers . . . . .	102
Installing Dimensions Published Views . . . . .	102
Setting Configuration Variables . . . . .	103
Web Client Acceptance Tests . . . . .	103
Administration Console Acceptance Tests . . . . .	104
File System Considerations for Server Binaries . . . . .	104
SQL Server Enterprise Memory Usage . . . . .	105
Directories for Process Model Demo Products . . . . .	105
Configuring Trusted Certificate Authorities . . . . .	105
Dual Authentication . . . . .	109
Establishing a Certificate Revocation List . . . . .	109
Adding Smart Card Authentication . . . . .	110
SBM Smart Card Configuration Symbols . . . . .	112
Integrating with Dimensions RM . . . . .	112
Create User Accounts . . . . .	113
Specifying a Whitelist of CM Server Connections . . . . .	113
Deployment Automation Tasks . . . . .	113
Agent Post-Installation Tasks . . . . .	113
Agent Acceptance Tests . . . . .	113
Error Messages in Server Event Viewer . . . . .	114
Client Post-Installation Tasks . . . . .	114

Checking the PATH Environment Variable . . . . .	114
Using Internet Explorer to Access the Web Client . . . . .	114
Setting Up Aliases to Access Remote Databases . . . . .	115
Setting Up Access to Item Libraries on Remote Hosts . . . . .	115
Importing Visual Studio Customizations . . . . .	115
Setting Up the Dimensions SCC Interface . . . . .	115
Setting Configuration Variables . . . . .	116
PowerBuilder Issues on Windows Server . . . . .	116

## Chapter 7

<b>Pre-Upgrade Tasks . . . . .</b>	<b>117</b>
General Pre-Upgrade Tasks . . . . .	118
Upgrading from Dimensions CM 2009 R2 and 12.x . . . . .	120
Back up your Installation . . . . .	122
SSO Server Tasks . . . . .	123
SBM SSO Server Tasks . . . . .	123
Dimensions CM SSO Server Tasks . . . . .	123
Further Information . . . . .	124
Upgrading Deployment Areas . . . . .	124
Upgrading the Eclipse Integration or Dimensions Make . . . . .	124
Upgrading 2009 R2 Clients on Windows 64-Bit . . . . .	125
Shut Down Dimensions CM . . . . .	125
Closing the Microsoft Management Console . . . . .	125
Verify the Database is Running . . . . .	126
Download the Installer . . . . .	126

## Chapter 8

<b>Upgrading Dimensions CM . . . . .</b>	<b>127</b>
Upgrade Options . . . . .	128
Pre-Upgrade Tasks . . . . .	128
Running the Installer . . . . .	129
Running the Installer from a DVD . . . . .	129
Running the Installer from a Download . . . . .	129
Upgrading all Server Components . . . . .	130
SSO and Smart Card Limitations and Requirements . . . . .	130
Upgrading a Server with a PostgreSQL Database . . . . .	130
Upgrading a Server with an Oracle Database . . . . .	133
Upgrading a Server with an SQL Database . . . . .	136
Upgrading a Server Only . . . . .	138
Upgrading Windows Agents . . . . .	139

Upgrading Windows Clients . . . . .	140
Verifying an Upgrade . . . . .	141
Upgrading a Database . . . . .	141
Typical Upgrade Scenario . . . . .	141
Upgrade Path . . . . .	142
Silently Upgrading Agents . . . . .	142
Silently Upgrading Clients . . . . .	143
Post-Upgrade Tasks . . . . .	143

## Chapter 9

<b>Post-Upgrade Tasks . . . . .</b>	<b>145</b>
Testing the Installation . . . . .	146
Updating Tomcat Installations . . . . .	147
Recalculating Database Statistics . . . . .	147
Configuring a Deployment Server . . . . .	147
Upgrading Pre-14.x Data . . . . .	148
Using the VRS Upgrade Utility . . . . .	148
Using dmdba to Upgrade to VRS . . . . .	149
Computing Statistics . . . . .	150
Server Post-Upgrade Activities . . . . .	150
Updating Database Views . . . . .	150
Reinstalling Dimensions Published Views . . . . .	152
Rebuilding Developer Toolkit Applications . . . . .	152
SSO SBM Server Tasks . . . . .	152
SSO and Smart Card Tasks . . . . .	152
Visual Studio Customizations . . . . .	154
Migrating Pre-Dimensions 12 Deployment Data . . . . .	154
Preparing for Migration . . . . .	155
Running the Migration Process . . . . .	156
Upgrading and Maintaining the MO_LIST Table . . . . .	158

## Chapter 10

<b>Uninstalling Dimensions CM . . . . .</b>	<b>173</b>
Introduction . . . . .	174
Uninstalling Components . . . . .	174
Stopping Services . . . . .	174
Removing Programs . . . . .	175
Undeleted Files . . . . .	175
Undeleted Registry Keys . . . . .	176
Uninstalling the Eclipse Integration . . . . .	176



	Manually Uninstalling Windows Clients. . . . .	176
	Clearing Up Files . . . . .	176
	Clearing Up Environment Variable . . . . .	177
	Completing the Uninstallation Procedure . . . . .	177
<i>Chapter 11</i>	<b>Item Library Security on NTFS Server. . . . .</b>	<b>179</b>
	Protecting Item Libraries . . . . .	180
	Library Access Process . . . . .	180
	Item Library Node Location . . . . .	181
<i>Chapter 12</i>	<b>Troubleshooting. . . . .</b>	<b>183</b>
	Troubleshooting Installation Issues . . . . .	184
	Installation Logs. . . . .	184
	Dimensions Listener . . . . .	184
	Troubleshooting a Windows Server . . . . .	191
	Installation Problems . . . . .	191
	Connection Problems . . . . .	192
	Miscellaneous . . . . .	192
	Enabling Dimensions Listener Tracing . . . . .	192
	Extracting Windows-Based Directory Items on Solaris . . . . .	193



# Chapter 1

---

## Getting Started

Supported Platforms and Integrations	12
Licensing with APLS	12
General Information	12
Logging Pre-Installation Information	13
Useful Information	14

## Supported Platforms and Integrations

For details about platforms, upgrades, databases, and third-party integrations supported by OpenText™ Dimensions CM, see the [Support Matrix](#).

For details about hardware scaling and optimization, see the architecture and optimization information in the [Dimensions CM online help](#).

## Licensing with APLS

Dimensions CM uses the OpenText™ AutoPass License Server (APLS) to organize and manage licenses.

**NOTE** Dimensions CM no longer supports licensing with SLM.

You can install Dimensions CM with a 30-day evaluation option or a full license:

- If you install with a **30-day evaluation option**, you can use the software immediately, and no configuration is required. After the evaluation period expires, you need to upgrade to a full license.

The evaluation license does not support Dimensions Replicator.

- If you install with a **full license**, you need to install AutoPass and configure Dimensions CM to use it.

To install APLS, run an installer on a designated machine, or set up APLS as a Docker image.

By default, APLS is set up to accept connections via HTTPS only. After you install APLS, configure Dimensions CM to use AutoPass. For details, see the [Dimensions CM online help](#).

## General Information

- If you are installing server and client binaries on the same Windows machine, you must install the server first. The client installer detects that you have the server installed on your machine.

- 
- On a 64-bit Windows server the 32-bit client installer sets the target folder by default to:

C:\Program Files (x86)\OpenText\Dimensions <version>\CM

- Check that all Windows programs are shut down before beginning the installation including background programs such as virus checkers. If you do not shut down these programs the installation may fail.
- If you are installing clients on a Windows machine with high default security settings you may receive warnings similar to this:

*Some files can harm your computer...*

*Program needs your permission to continue.*

Click **Open** or **Continue** to proceed with the installation.

- Depending on your browser and its settings the following messages may be displayed:

*File Download - Security Warning message Do you want to run or save this file?*

Click **Run** to continue.

*Internet Explorer - Security Warning message The publisher could not be verified...*

Click **Run** to continue.

## Logging Pre-Installation Information

### Server

Log the following server information:

- Database password that is assigned to SYSTEM.
- Database password that is assigned to PCMS\_SYS.
- OS username to be used for the Dimensions system administrator (typically *dmsys*).
- Name of the process model to be installed (server plus schema installations only).

## SSO and Smart Card

For an existing Single Sign On (SSO) server log the following:

- Host name
- SSO port
- If a secure (https) connection is required

For a new SSO server log the following:

- Host name
- SSO port
- Bind user DN
- LDAP password for the bind user DN
- LDAP parameters to be used:
  - Host name (by default same as for smart card reader)
  - Port (by default same as for smart card reader)
  - Base DN
  - Search filter
  - Bind user DN (by default same as for smart card reader)
  - LDAP password for the bind user DN (by default same as for smart card reader)

## Useful Information

### Default Installation Locations

#### Dimensions CM

C:\Program Files\OpenText\Dimensions <version>\cm

#### Tomcat

C:\Program Files\OpenText\common\tomcat\<tomcat-version>

---

## OpenText PulseUno

C:\ProgramData\OpenText\Dimensions CM\Pulse

## CM Bridge

C:\ProgramData\OpenText\Dimensions CM\Bridge

## Install logs

- C:\Program Files\OpenText\Dimensions<version>\CM\InstallTemp
- C:\Users\<user who installed CM>\AppData\Local\Temp

## Clients

- Dimensions 14 works with 12.2.2.x clients. We recommend to upgrade the clients to match the Dimensions CM server version as soon as possible.
- The clients are 32-bit applications, and the files are saved in C:\Program Files (x86).
- The Windows Explorer plugin is installed as a 64-bit or 32-bit application depending on your operating system.
- If you are installing the clients on the same machine as the server, do not use the same directories, as unexpected results may occur.

## Agents

- We recommend to upgrade the agents to match the Dimensions CM server version as soon as possible.
- The agent is a 32-bit application and the files are saved in C:\Program Files (x86).
- An agent is a subset of a server and is not required if a server is installed. If you install an agent on the same machine as a server, unexpected results may occur.

## OpenText PulseUno

PulseUno is a Tomcat web application that is automatically installed under the Tomcat directories. You can optionally install the PulseUno modules, the Git and Vault servers. To access PulseUno, use this URL:

`http(s)://<CM_Server>:8080/pulse`

## CM Bridge

CM Bridge is a Tomcat web application that is automatically installed under the Tomcat directories. To access CM Bridge, use this URL:

`http(s)://<CM_Server>:8080/cmbridge/QLARIUS`

See the *CM Bridge Guide* for details.



## Chapter 2

---

# Migrating from Serena Runtime to PostgreSQL

Installing your own PostgreSQL	18
Migration Steps	18

---

## Installing your own PostgreSQL

PostgreSQL is bundled with the Dimensions CM server installer. Dimensions CM also supports commercial and open-source PostgreSQL distribution. For example, you can download PostgreSQL from:

- EDB Postgres  
<https://www.enterprisedb.com/downloads/postgres-postgresql-downloads>
- PostgreSQL  
<https://www.postgresql.org/download>

PostgreSQL installation steps:

[https://wiki.postgresql.org/wiki/Detailed\\_installation\\_guides](https://wiki.postgresql.org/wiki/Detailed_installation_guides)

For details about supported PostgreSQL versions, see the [Support Matrix](#).

## Migration Steps

Follow these steps to migrate from the Serena-Supplied Runtime to PostgreSQL on the same machine. These steps may differ if your environment has multiple machines.

- 1 Back up your existing RDBMS database using database tools. See the *Administration Guide*.
- 2 Back up item libraries using operating system tools.
- 3 Upgrade your current Dimensions CM system to the latest version (see [page 127](#)).
- 4 Check that NLS\_LANG matches your database character set, for example:  
  
`set NLS_LANG=AMERICAN_AMERICA.AL32UTF8`
- 5 Export the PCMS\_SYS schema from Oracle using the dmdba export facility, for example:

---

```
dmdba --noschemacheck
pcms_sys/<pcms_sys_password>@<dsn> export_dm_sys
/EXPORT_FILE="c:\dumps\pcms_sys_export.sql"
```

- 6** Export each base database from Oracle using the dmdba export facility, for example:

```
dmdba system/<system password>@<dsn> export_base_tables
/EXPORT_FILE="c:\dumps\export.sql"
/basedb=cm_typical
/target=postgresql
```

Repeat this process for each database that you want to migrate.

- 7** Export the PulseUno database from Oracle, for example:

```
dmdba --noschemacheck system/<system password>@<dsn>
export_pulse_tables
/EXPORT_FILE="c:\dumps\pulse_export.sql"
/dbname=pulse
/target=postgresql
```

- 8** Uninstall your Dimensions CM server (see [page 173](#)).
- 9** Install the latest Dimensions CM server with PostgreSQL. Use your own PostgreSQL or the one bundled with the installer (see [page 59](#)).
- 10** Check that the following services have started:
- OpenText Common Tomcat <version>
  - Dimensions CM listener

- 11** Stop both of these services.

- 12** Drop the newly created base database:

```
dmdba postgres/<password>@<dsn>
DLDB cm_typical
```

You only need to drop the `cm_typical` database if you are migrating it from Oracle to PostgreSQL.

- 13** Prepare the PulseUno database to receive your PulseUno export file:

```
dmdba postgres/<password>@<dsn> grant_pcms_sys pulse
dmdba --noschemacheck pulse/<pulse password>@<dsn>
```

```
truncate_pulse_tables
```

- 14** Import the PCMS\_SYS export file that you exported earlier:

```
dmdba --noschemacheck
pcms_sys/<pcms_sys_password>@<dsn>
@c:\dumps\pcms_sys_export.sql
```

- 15** Import the base databases:

```
dmdba postgres/<password>@<dsn>
crdb cm_typical
/toolman=dmsys
/import="c:\dumps\export.sql"
/installviews
```

Repeat this process for each database that you want to import.

- 16** Import the PulseUno export file, for example:

```
dmdba --noschemacheck pulse/<pulse password>@<dsn>
@c:\dumps\pulse_export.sql
```

- 17** Generate statistics for the imported databases:

```
dmdba postgres/<password>@<dsn>
connect <base database name>
STATISTICS COMPUTE
```

- 18** Restart the Dimensions CM services.

#### **NOTE**

- PulseUno chains that you imported with the base database may not run as scheduled. Edit each chain and reconfigure its schedule.
- If you migrate to a different machine, or change the database connection string, you must update all configuration and administration settings, for example:
  - listener.dat and other configuration files.
  - Dimensions CM server name and base database in PulseUno.
  - Item library server name in the Administration Console.
- Review your custom command line scripts, API programs, and web service integrations for any database specific tools and settings. For example, if you are running SQL\*Plus, use the PostgreSQL interactive terminal instead.

---

## Chapter 3

---

# Pre-Installation Tasks

Prerequisites	22
Server and Agent	22
Remote UNIX Agents and Clients	26
Windows Clients	27
SSO and Smart Card Authentication	28
Networking Tasks	33
Integrations	35
Closing the Microsoft Management Console	38

## Prerequisites

- Back up your Windows registry.
- A fresh server installation requires 10 GB of disk space.
- You need 5 GB of temporary working space on the C:\ drive.
- You can install the Rational Doors integration only on a machine where a Dimensions CM client is installed (not a server or agent).
- You can use files up to 4 GB in size. For details, see the `pcms_item_data` published view in the *Reports Guide*.
- The installation folder that you select must not be at the root of the file system area, for example, C:\.

## Server and Agent

### Installing on the Same Machine

If you are installing a server/agent and client on the same Windows machine you must install the server/agent first. The client installer detects the server is installed.

- For all supported Windows platforms, apart from 64-bit Windows server, the client installer sets the target folder to the existing Dimensions CM server home folder.
- On a 64-bit Windows server the client installer sets the target folder by default to (the clients are 32-bit):

`C:\Program Files (x86)\OpenText\Dimensions <version>\CM`

### Checking the Database is Active

Before running a server installation, check that the local or remote database to be used by Dimensions CM is active by establishing that you can connect to it using standard RDBMS database utilities.

---

Also confirm, using standard RDBMS database utilities, that you know the correct database passwords for SYSTEM (Oracle Enterprise) or PCMS\_SYS (SQL Server).

## Creating an Administrator Account

Before installing Dimensions CM you must create an operating system user account for the Dimensions system administrator, typically `dmsys`. During the installation you need to provide the credentials for this account.

### NOTES

- The Dimensions system administrator is the Windows user who owns the CM files and starts processes. Dimensions CM works with a system administrator who is a regular Windows user (does not have Windows administrator privileges). However, the system administrator can be a member of the Windows Administrator group. This may be necessary for logging, for example, obtaining command audit logging that has been set in the `dm.cfg` file.
- For Oracle Enterprise, the primary group-id for `dmsys` must be the same group-id as the Oracle instance owner's group-id (for example, `dba`).
- See the *Administration Guide* for details about Dimensions system administrator.

Depending on which process model you chose during installation, it may be convenient for you to also set up the additional operating-system user account names that the process model utilizes.

## Choosing a Process Model

During a fresh installation of a Dimensions CM server with a schema you are prompted to select a process model:

### ***Typical, Stream Development***

Deploys the *Typical, Stream Development* process model and an associated sample Dimensions CM product called *Qlarius* containing stream development features.

This model is a "copy, modify, merge" methodology for managing modern, Agile parallel development, or if migrating from a tool like Subversion.

### ***Typical, Non-Stream Development***

Deploys the *Typical, Non-Stream Development* process model and an associated sample Dimensions CM product called *Qlarius* containing non-stream development features.

This model is a "lock, modify, unlock" methodology for managing more traditional waterfall development, or migrating from a tool like CVS or PVCS Version Manager.

### ***Intermediate***

Deploys the *Intermediate* process model and an associated sample product called *Payroll*. This is a legacy process model.

### ***Custom***

This process model has no pre-defined roles and no associated sample product. It is intended for use by:

- Consultants and experienced Dimensions CM users to facilitate the definition of their own workflow model, without the overhead of having to delete definitions from pre-loaded process models.
- Existing users of Dimensions CM who have created their own process model export file that they want to import during Dimensions CM base database creation.

This model is also available by choosing the import option when using the Dimensions CM `dmdba crdb` function. For details, see the *Administration Guide*.

We strongly recommend to check with Support about the validity of a process model before attempting to import it.

## **Adding Database Process Models**

You can install additional process models post-installation using the `dmdba CRDB` command. For details, see the administering Dimensions CM schemas section in the *Administration Guide*.



---

## TCP/IP Port Usage

### ***Web Tools Port***

During server installation TCP/IP port 8080 is assigned to the web tools. Verify that this port is not already being used by other software. Some software is hard coded to port 8080 and cannot be reassigned. If port 8080 is not available, you can specify an alternative port during installation.

**IMPORTANT!** If a server is behind a firewall the port must allow traffic in both directions.

### ***Dimensions CM Listener Port***

By default the Dimensions CM listener port is set to 671.

### ***Secure Sockets Layer Ports***

The web tools also configures two Secure Sockets Layer (SSL) ports:

- 8443: a general port for HTTPS/SSL connections and the sample Dimensions CM SSL certificate.
- 8543: a port for HTTPS/SSL connections that are used to perform smart card authentication.

## NTFS File System for Server Binaries

The Windows server NTFS file system is recommended for the disk file system on which the server binaries installed, for details see [page 179](#).

## SMTP Server Details

If you have a Simple Mail Transfer (SMTP) email system on your network you can optionally enter the server details during the installation. See the *Administration Guide* for details about configuring your emailing software after installation.

## Multiple Oracle Homes

The Oracle RDBMS supports multiple Oracle homes. When an existing Oracle server is detected during installation you are prompted to select one as the home for Dimensions CM.

## Remote UNIX Agents and Clients

(Clients only) TCP/IP must be pre-installed on the recipient node.

### Open Motif Package on Linux Agent

On Red Hat Linux, SuSE Linux, and SuSE zLinux the Dimensions client and agent require the Open Motif package to be pre-installed, for example, `openmotif-devel-XXX.rpm`. Use the Yast2 utility or an equivalent Linux tool.

### Security on Red Hat Enterprise Linux

For Red Hat Enterprise Linux 5.5 and 6.x, as user root run the Red Hat System Level Configuration Tool:

```
# system-config-securitylevel
```

Check that these settings are disabled:

- Firewall
- SE Linux (Security Enhanced Linux)

If the settings are not disabled the following error message is displayed when you run `dmcli` after installing CM (even though the Dimensions listener runs correctly):

---

```
$ dmcli
License Server: createJob failed: -2
License Server: createJob failed: -2
ACL4500017E Error: Cannot open
```

The licence server is running.

**IMPORTANT!** Disabling the firewall and SE Linux may go against your security policies.

## Windows Clients

- TCP/IP must be preinstalled on the recipient node.
- For details about installing a server and clients on the same machine, see [page 22](#).
- To use the Dimensions CM ART or directory item functionality, install a Windows version of the UNIX tar utility on the client machine. You can download a free version from the Cygwin website.

Copy the required packages to %DM\_ROOT\prog after you install CM.

# SSO and Smart Card Authentication

Support for Single Sign On (SSO) authentication is optionally available on certain Dimensions CM platforms by editing various configuration files post-installation. For details, see the *Administration Guide*.

On platforms that support SSO you can:

- Install an SSO server with a Dimensions CM server.
- Using an existing SSO server, for example, an SSO-enabled SBM server installation.
- Configure smart card reader server-side software.

The Dimensions CM installer performs most of the configuration however you do need to enter SSO values, see below for details.

The installer configures CM to work with SSO and smart cards apart from trusted certificate authorities that you configure manually, see [page 105](#).

**NOTE** We recommend installing an SSO server and smart card at the same time that you install the server to take advantage of the automatic configuration.

## Existing SSO Server Prerequisites

The following information is requested by the installer when you select an existing local or remote SSO server:

Existing SSO Parameter	Description
Hostname	Host name of the existing SSO Server.
SSO Port	HTTP or HTTPS TCP port used by the existing SSO server. If the port is not HTTPS do not select <b>Secure (https) Connection</b> .
Secure (https) Connection	Default: not selected. Select if Secure Socket Layer (SSL) communication is required.

You can download the SBM software and documentation from the Support website. To enable an SBM server for SSO, see the *SBM Installation and Configuration Guide*.

---

## Smart Card Prerequisites

The following information is requested by the installer when you configure smart card authentication for the first time:

Base Authentication Method	Smart Card Parameter	Description
Light Directory Access Protocol (LDAP)	Hostname	Either the host name of the Domain Controller (Active Directory) or the machine that serves LDAP requests. It is usually the former.
	Port	TCP port (by default 389) to be used by the new SSO server.
	Bind User DN	<p>The LDAP bind user distinguished name (DN) to be used for smart card configuration.</p> <p>The bind user DN is the user on the external LDAP server permitted to search the LDAP directory within the defined search base. Most of the time, the bind DN is permitted to search the entire directory. The role of the bind DN is to query the directory using the LDAP query filter and search base for the DN (distinguished name) for authenticating users. When the DN is returned, the DN and password are used for authentication.</p>
	Password	The LDAP password to be used in conjunction with the bind user DN by the new smart card setup software.

# New SSO Server Prerequisites

The following information is requested by the installer when you create a new local or remote SSO server:

Base Authentication Method	SSO Parameter	Description
Native Windows Authentication (NTLM)	Hostname	Host name on which to install the new SSO server.
	Domain	The server domain in which the Windows users reside.
Lightweight Directory Access Protocol (LDAP)	Hostname	Either the host name of the Domain Controller (Active Directory) or the machine that serves LDAP requests (typically the domain controller).
	Port	TCP port to be used by the new SSO server. Default: 389
	Base DN	The LDAP base DN to be used by the new SSO server. The base DN is the top level in the LDAP directory tree below which the search for the user is performed. For example:  CN=Users , DC=your , DC=domain , DC=com

Base Authentication Method	SSO Parameter	Description
Light Directory Access Protocol (LDAP) (continued)	Search Filter	<p>The LDAP search filter to be used by the new SSO server. The installer pre-populates with a default search filter.</p> <p>LDAP search filters function within a framework. The framework includes what attributes you are searching on and the value, or range of values, that you are trying to match. Each search filter involves at a least three components:</p> <ul style="list-style-type: none"> <li>■ The attributes to search for, called the <i>attribute data type</i>.</li> <li>■ The search filter operator that determines what to match, sometimes called the <i>match operator</i>.</li> <li>■ The actual value of the attribute you are searching for.</li> </ul> <p>Each search needs to have a minimum of one of each of the components. You can create compound search filters by connecting two or more search filters modules. They are enclosed in parentheses to clarify filter content and include one or more of three compound search filter operators (AND, OR, NOT). You can add as many compound and wild card filters as needed provided you have the correct number of matching parentheses.</p> <p>The actual search filter in the case of Microsoft Active Directory (Domain Controller) should look like:</p> <pre>(&amp;(objectClass=user)(sAMAccountName={0}))</pre> <p>where {0} is substituted by the actual user name that is logging in.</p>

Base Authentication Method	SSO Parameter	Description
Light Directory Access Protocol (LDAP) (continued)	Search Filter (continued)	See the <i>LDAP RFC 4515 documentation</i> for more information about LDAP search filters and a mechanism for representing them as strings.
	Bind User DN	<p>The LDAP bind user DN to be used by the new SSO server.</p> <p>The bind user DN is the user on the external LDAP server permitted to search the LDAP directory within the defined search base. Most of the time the bind DN is permitted to search the entire directory. The role of the bind DN is to query the directory using the LDAP query filter and search base for the DN for authenticating users. When the DN is returned, the DN and password are used for authentication.</p>
	Password	The LDAP password to be used in conjunction with the bind user DN by the new SSO server. By default, the installer pre-populates this field with same LDAP value it was given earlier for the smart card setup software.

## Smart Card Client Prerequisites

- Smart card ActivClient 6.1 or later is installed and configured on each client. For details about logging in using your smart card see the *Dimensions CM User's Guide*.

If you have Version 6.2 of ActivClient installed, to use a smart card with the Eclipse integration you need to change the location of the SmartCard Library. For details, see [page 212](#).

- Each user has a personal smart card.
- A smart card reader is attached to the client machine.



---

# Networking Tasks

## Network Nodes Types

- **Server node**

Accesses the database, can host item libraries and work/deployment areas, and includes the command-line client.

- **Listener node**

Can host item libraries and work/deployment areas but has no access to the database and no clients.

- **Client node**

Clients only.

## Optimizing Network Performance

Database processes should run on the fastest node in the network and, if possible, the node should have no Dimensions CM logins on it. The OS parameters should be optimized with as much RAM as possible for each Dimensions CM network node in the network. If a single user workstation is used on the network, appropriate resources may need to be significantly increased to reduce paging/swapping.

In addition to providing networking facilities to permit operations across both a homogeneous and heterogeneous environment, a Dimensions CM network is able to spread the processing load. See the section about using and configuring library cache in the *Administration Guide*.

To optimize your network, see the *Dimensions CM online help*.

## Network Disk Distribution

Disk access speed can significantly affect performance. We recommend splitting server configuration across multiple disks to improve performance.

### ***Summary of Multi-Disk Configurations***

To provide the best disk performance, we recommend the following:

- Windows Microsoft SQL Server, four disks
  - Disk1            Windows System disk
  - Disk2            Page and swap file
  - Disk3            User files
  - Disk4            Database files only (RDBMS)
  
- With Oracle Enterprise on Windows or UNIX, five disks:
  - Disk1            UNIX or Windows System disk
  - Disk2            Page and swap file
  - Disk3            User files
  - Disk4            Database files only (RDBMS)
  - Disk5            Redo log files (RDBMS), if applicable

**Detailed Multi-Disk Configurations**

The tables below shows recommend disk usage in a number of configurations. The goal is to balance the load across all available disks.

- Windows Microsoft SQL Server RDBMS.

	One Disk	Two Disks	Three Disks	Four Disks
System Disk	D1	D1	D1	D1
Page and Swap files	D1	D1	D3	D3
User files	D1	D2	D2	D2
Database files	D1	D2	D3	D2
Dimensions CM Programs	D1	D1	Any	Anywhere but the System Disk
Item Libraries	D1	D2	Not D1	
Database programs	D1	D1	Any	

- UNIX or Windows Oracle Enterprise RDBMS

	One Disk	Two Disks	Three Disks	Four Disks	Five Disks
System Disk	D1	D1	D1	D1	D1
Page and Swap files	D1	D1	D3	D3	D3
User files	D1	D2	D2	D2	D2
Database files	D1	D2	D2	D2	D5
Redo log files	D1	D1	D3	D4	D4
Dimensions CM Programs	D1	D1	Any	Anywhere but the System Disk	
Item Libraries	D1	D2	Not D1		
Database programs	D1	D1	Any		

The database files are associated with separate tablespaces PCMS\_TEMP, PCMS\_RBS, PCMS\_DATA, and PCMS\_IDX.

## Item Library Host Performance

Item libraries should be hosted on nodes that can handle the load and that are local to the users that most often require access to them.

## Integrations

For details about the supported versions of integration tools, see the [Support Matrix](#).

## Eclipse

Eclipse must be installed on the target platform (a local Windows or a remote UNIX machine).

## Visual Studio

Visual Studio must be installed on the target platform.

### ***Exporting and Importing Customizations***

Installing the Visual Studio integration deletes existing Visual Studio customizations. You can export your current customizations before installing the integration:

- 1 Tools | Import and Export Settings
- 2 Follow the instructions of the Microsoft Import and Export Wizard to export your customizations.

Visual Studio automatically exports customizations, but we recommend exporting your customizations. After you have installed the integration use the Microsoft Import and Export Wizard to import your customizations.

You also need to migrate your Visual Studio solutions controlled by Dimensions SCC into solutions compatible to the new Visual Studio integration by using the migration tool.

## Dimensions CM Connect for SBM

To continue using the Dimensions CM Connect for Solutions Business Manager (SBM) synchronization integration, certain Windows registry keys are set to the last synchronization every time a synchronization occurs. These keys should be maintained for as described below. If not, the updated integration restarts from the "epoch" (1970-01-01).

- 1 (Recommended) Backup your registry.
- 2 Open regedit.
- 3 Navigate to the following registry hive:  
`HKEY_LOCAL_MACHINE\SOFTWARE\Serena\Dimensions Connect for Business Mashups\<link_no>`
- 4 Log the values of the keys below or export the parent hive to a file using the registry export command so that you can import them after installation the integration:

- 
- DM Last Timestamp
  - TT Last Timestamp

### ***Changing the Location of Temporary Files***

Running the SBM-to-Dimensions connector produces numerous temporary files. These include temporary attachment files created during the transfer from SBM to Dimensions of:

- detailed descriptions (DM\_ATTR\_DD)
- file attachments (TS\_ATTACHATTRIB\_FILE and TS\_ATTACHATTRIB\_SHOWIMAGE)
- notes (TS\_ATTACHATTRIB\_NOTE)
- URLs (TS\_ATTACHATTRIB\_URL)

The default location for temporary attachment files is the `Attach.Tmp` folder in the installation folder. You can use the Windows registry to change the location for these files.

The `HKLM\SOFTWARE\Serena\Dimensions Connect for Business Mashups\TmpAttachmentsDir` registry key explicitly defines a folder for temporary attachment files. If the specified folder does not exist, it is created and registered in the current log file (the parent folder must exist). You can create a subkey in the registry that looks like this:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Serena\Dimensions Connect for  
Business Mashups\TmpAttachmentsDir="C:\TTDM.Temp"
```

Note that the `TTDmSyncService.exe` program normally deletes temporary files for new and updated SBM issues when current SBM issue transfer is complete.

The `TTDmSyncService.exe` program writes the names of successfully created temporary files to a separate log file. The default location is `TmpFile.log` in the installation folder. You can change this location using the `HKLM\SOFTWARE\Serena\Dimensions Connect for`

Business Mashups\TmpFileLog registry key by creating a subkey that looks like this:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Serena\Dimensions Connect for  
Business Mashups\TmpFileLog="C:\Program  
Files\OpenText\Dimensions  
<version>\CM\Integrations\Business  
Mashups\SBMAAttachments.log"
```

To disable the temporary file log set the HKLM\SOFTWARE\Serena\Dimensions Connect for Business Mashups\TmpFileLog registry key to the empty string.

To simplify diagnosis of temporary file issues, the current log file contains file system error descriptions together with file names and attachment types.

**NOTE** There are other temporary files that, by default, are placed in the folder specified by the system's TEMP or TMP environment variable. These temp files are not automatically deleted and may need to be cleaned up periodically. To change the location for these files, edit the DM\_TMP variable within the dm.cfg file and then restart your services. Stop the Sync Service before stopping the Dimensions Listener Service.

## Closing the Microsoft Management Console

Close the Microsoft Management Console before installing.

## Chapter 4

---

# Preparing a Database

Introduction	40
Preparing an Oracle Database	41
Preparing an SQL Server	49
Oracle Multi-Byte Character Sets	55
Preparing a PostgreSQL Database	56

# Introduction

A Windows CM server requires access to one of these databases:

Database Type	OS	See
Oracle Enterprise	Windows	<a href="#">page 41</a>
SQL Server Enterprise	Windows	<a href="#">page 49</a>
PostgreSQL	Windows	<a href="#">page 17</a>
Oracle Enterprise and PostgreSQL	UNIX	<i>Installation Guide for UNIX</i>

## NOTE

- Dimensions RM supports the Oracle AL32UTF8 character set and all data entered must be ASCII characters for Dimensions RM to display it correctly. If you intend to use Dimensions RM to access data entered in a Dimensions CM AL32UTF8 database, that data must also be entered as ASCII. This is particularly important for project, stream, and product names.
- Allocate at least 1GB of memory as the Oracle System Global Area (SGA) target size. Oracle recommends allocating 40-50% of available memory for the SGA.
- Dimensions CM for Windows supports these database connectivity methods:
  - Oracle: OCI
  - Microsoft SQL Server: ODBC



---

# Preparing an Oracle Database

## Local Oracle Enterprise

### *Upgrading an Oracle Instance*

If your Oracle Enterprise database contains an Oracle instance with a Dimensions CM schema, the server installation detects and automatically upgrades the schema and installs the required Oracle tables.

### *Creating a Fresh Oracle Instance*

To create a fresh instance in your Oracle Enterprise database, install the supplied template file and run the Oracle Database Configuration Assistant (DBCA) using the template file to create an instance.

- 1 Copy the appropriate template file to this folder:

`%ORACLE_HOME%\assistants\dbca\templates`

The database template files are located in: `db_preinstall\oracle`

The template files are:

- 11gR2.0.3: `SerenaOracle11g.dbt`
- 12.1.0.1: `SerenaOracle12c.dbt`
- 12c: `SerenaOracle12102.dbt`
- 12.1.0.2: `SerenaOracle12102.dbt`
- 12.1.0.2 (CM and SBM in the same Oracle instance):  
`SerenaOracle12102CMSBM.dbt`
- PDB (for creating multitenant container databases with any version of Oracle): `MicroFocusOraclePDB.dbt`

- 2 Go to Start | Oracle `<oracle_home>` | Configuration and Migration Tools | Database Configuration Assistant

**NOTE** The following instructions are applicable to the version of DBCA in Oracle 12c.

- 3 On the Database Operation page, select **Create Database**.
- 4 On the Creation Mode page, select **Advanced**.

- 5 On the Database Template page, select the required template.  
To create a pluggable database (PDB), select the `pdb_dim14` template.
- 6 On the Database Identification page, enter the Global Database Name and the Oracle SID (Oracle System ID). The former is limited to eight characters the first of which must be alphabetic. If the Oracle SID is eight characters or less you can assign the same name to both fields.

**To create a container database:**

- a Verify that the **Create as Container database** option is selected.
- b Select **Use Local Undo tablespace for PDBs**.
- c Select the **Create a Container database with one or more PDBs** option.
- d Set the **Number of PDBS** to 1.
- e Enter a name for the PDB, for example, `pdb_dim14`.
- 7 On the Management Options page, specify options for managing the database.
- 8 On the Database Credentials page, specify passwords for the user accounts. Set the passwords in accordance with your site policies and log the values for future reference.
- 9 On the Network Configuration page, select a current Oracle listener or create a new one.
- 10 On the Storage Locations page:
  - Select the storage type and locations for database files. From the **Database files Storage Type** list, select **File System**.
  - Accept the defaults for the common location of all database files or specify values supplied by your DBA.
  - Accept the default database recovery options and deselect **Specify Fast Recovery Area** or specify values supplied by your DBA.
- 11 On the Database Options page, optionally select database components, sample schemas, and custom scripts.

- 
- 12** On the Initialization Parameters page, accept the default values for Memory, Sizing, Character Sets, and Connection Mode or specify values supplied by your DBA.
  - 13** On the Create Options page, check that **Create Database** is selected.
  - 14** On the Prerequisite Checks page, check the database validation results and any warnings.
  - 15** On the Summary page, review the settings and click **Finish** to create the database instance.

After the instance is created, verify the connection to your database.

**To verify the connection to the instance:**

- 1** Open a command prompt.

- 2** Enter:

```
sqlplus system/<system_password>@<ora_instance>
```

For the container database, specify the <ora\_instance> as the PDB name, for example, pdb\_dim14.

- 3** Check the output to confirm that you have successfully connected.

If sqlplus fails to connect to the container database, verify that a connector for the PDB name is defined in the `tnsnames.ora` file, for example:

```
PDB_DIM14 =
  (DESCRIPTION =
    (ADDRESS = (PROTOCOL = TCP)(HOST = <host name>)(PORT = 1521))
    (CONNECT_DATA =
      (SERVER = DEDICATED)
      (SERVICE_NAME = PDB_DIM14)
    )
  )
```

- 4** To exit SQL, enter `exit`.

**Container database:** After the connection is established, save the access states and create tablespaces.

**To save the container database access states and create tablespaces:**

A container database is created with Open, Read and Write access, but these access states are not stored as the default. Before you stop or restart the database, make sure to save the access state.

Additionally, when you create a container database, the tablespaces are not created by the Oracle Database Configuration Assistant (DBCA). You need to create them manually.

To preserve the access state after a database restart, and create tablespaces, connect to the instance as the administrator and run the following commands:

**1 Save access states:**

```
$ sqlplus system/<system_password>@<dsn>
SQL> connect / as sysdba;
SQL> ALTER PLUGGABLE DATABASE pdb_dim14 OPEN READ WRITE;
SQL> ALTER PLUGGABLE DATABASE pdb_dim14 SAVE STATE;
```

**2 Create tablespaces, modifying the DATAFILE paths to suit your system:**

```
$ sqlplys system/<system_password>@<pdb_name>

SQL> CREATE BIGFILE TABLESPACE "PCMS_DATA" LOGGING DATAFILE
      'c:\oracle\oradata\DIM14\pcms_dat_8xxc593z.dbf' SIZE 512M REUSE
      AUTOEXTEND ON NEXT 100M MAXSIZE 65535M EXTENT MANAGEMENT LOCAL
      SEGMENT SPACE MANAGEMENT AUTO BLOCKSIZE 16384;

SQL> CREATE SMALLFILE TABLESPACE "PCMS_IDX" LOGGING DATAFILE
      'c:\oracle\oradata\DIM14\pcms_idx_8xxc6ox9.dbf' SIZE 512M REUSE
      AUTOEXTEND ON NEXT 100M MAXSIZE 65535M EXTENT MANAGEMENT LOCAL
      SEGMENT SPACE MANAGEMENT AUTO BLOCKSIZE 16384;

SQL> CREATE SMALLFILE TABLESPACE "PCMS_RBS" LOGGING DATAFILE
      'c:\oracle\oradata\DIM14\pcms_rbs_8xxc7no8.dbf' SIZE 512M REUSE
      AUTOEXTEND ON NEXT 100M MAXSIZE 65535M EXTENT MANAGEMENT LOCAL
      SEGMENT SPACE MANAGEMENT AUTO;

SQL> CREATE SMALLFILE TEMPORARY TABLESPACE "PCMS_TEMP" TEMPFILE
      'c:\oracle\oradata\DIM14\pcms_tem_8xxc4qdz.tmp' SIZE 512M REUSE
      AUTOEXTEND ON NEXT 100M MAXSIZE 65535M EXTENT MANAGEMENT LOCAL
      UNIFORM SIZE 1024K BLOCKSIZE 16384;
```

---

## Using an Existing Oracle Instance

To use an existing instance in your Oracle Enterprise database that is not based on a Serena-supplied database template, manually install the following Oracle tablespaces into your Oracle database:

PCMS\_DATA  
PCMS\_IDX  
PCMS\_TEMP  
PCMS\_RBS  
USERS

**NOTE** The Oracle database also requires either an UNDO tablespace or a tablespace dedicated to rollback segments (for example, PCMS\_RBS).

- 1 Connect to the Oracle instance where you want to install the schema:

```
$ sqlplus system/<system_password>@<dsn_name>
```

- 2 Create the Oracle tablespaces with minimum sizes indicated using the following sqlplus commands (substituting the folder pathnames appropriate to your system and sizes appropriate to PCMS\_TEMP on your system):

```
SQL> CREATE TABLESPACE "PCMS_DATA" DATAFILE  
      'D:\Oracle\Database\PCMS_DATA.DBF' SIZE 1000M REUSE AUTOEXTEND  
      ON;
```

```
SQL> CREATE TABLESPACE "PCMS_IDX" DATAFILE  
      'D:\Oracle\Database\PCMS_IDX.DBF' SIZE 1000M REUSE AUTOEXTEND  
      ON;
```

```
SQL> CREATE TABLESPACE "USERS" DATAFILE  
      'D:\Oracle\Database\USERS.DBF' SIZE 100M REUSE AUTOEXTEND ON;
```

```
SQL> CREATE TEMPORARY TABLESPACE "PCMS_TEMP" TEMPFILE  
      'D:\Oracle\Database\PCMS_TEMP.DBF' SIZE 200M AUTOEXTEND ON NEXT  
      160M MAXSIZE 2048M EXTENT MANAGEMENT LOCAL;
```

- 3 Create the following tablespace and rollback segments.

**NOTE** These commands are only applicable if you are using rollback segments rather than automatically managed UNDO tablespaces.

```
SQL> CREATE TABLESPACE "PCMS_RBS" DATAFILE  
      'D:\Oracle\Database\PCMS_RBS.DBF' SIZE 160M REUSE;
```

```
SQL >CREATE ROLLBACK SEGMENT "R0" TABLESPACE "SYSTEM" STORAGE (  
      INITIAL 20K NEXT 20K OPTIMAL NULL MINEXTENTS 2 MAXEXTENTS 20);
```

```
SQL> ALTER ROLLBACK SEGMENT "R0" ONLINE;
```

```
SQL> CREATE ROLLBACK SEGMENT "R01" TABLESPACE "PCMS_RBS" STORAGE (  
    INITIAL 1024K NEXT 1024K OPTIMAL 2048K MINEXTENTS 2 MAXEXTENTS  
    121);
```

```
SQL> ALTER ROLLBACK SEGMENT "R01" ONLINE;
```

```
SQL> CREATE ROLLBACK SEGMENT "R02" TABLESPACE "PCMS_RBS" STORAGE (  
    INITIAL 1024K NEXT 1024K OPTIMAL 2048K MINEXTENTS 2 MAXEXTENTS  
    121);
```

```
SQL> ALTER ROLLBACK SEGMENT "R02" ONLINE;
```

```
SQL> CREATE ROLLBACK SEGMENT "R03" TABLESPACE "PCMS_RBS" STORAGE (  
    INITIAL 1024K NEXT 1024K OPTIMAL 2048K MINEXTENTS 2 MAXEXTENTS  
    121);
```

```
SQL> ALTER ROLLBACK SEGMENT "R03" ONLINE;
```

```
SQL> CREATE ROLLBACK SEGMENT "R04" TABLESPACE "PCMS_RBS" STORAGE (  
    INITIAL 1024K NEXT 1024K OPTIMAL 2048K MINEXTENTS 2 MAXEXTENTS  
    121);
```

```
SQL> ALTER ROLLBACK SEGMENT "R04" ONLINE;
```

#### 4 Exit sqlplus:

```
SQL> exit
```

### ***Creating an Oracle ODBC DSN***

To optimize performance, by default Dimensions CM utilizes Oracle Call Interface (OCI) to access the database. If you use ODBC, create a system Oracle ODBC Data Source Name (DSN).

- 1 Log in as a user with local administrative privileges.
- 2 In Administrative Tools, open Data Sources (ODBC).
- 3 Select the **System DSN** tab and click **Add**.
- 4 In the Create New Data Source dialog box, select **Oracle** from the list of drivers and click **Finish**.
- 5 In the Oracle driver configuration dialog box, do the following:
  - a **Data Source Name:** Enter the DSN to use with your Oracle RDBMS. The DSN name must be the same as the Oracle service name.

---

Default: DIM14

- b Description:** Add a description for the DSN, for example, Oracle in Dimensions CM.
- c TNS Service Name:** Enter the name of the Oracle database from which the ODBC driver retrieves data, or select one from the list. To check the name of the database, in Administrative Tools open Services and look for the following service:  
  
OracleService<ora\_service\_name>  
  
where <ora\_service\_name> is the name of your Oracle Enterprise database.
- d** Click the **Workarounds** tab. If the option **Force Retrieval of Long Columns** is present select it.

**6** Click **OK**.

## Remote Oracle Enterprise

### *Using a Remote Oracle Enterprise*

You can install a server on the local node and install the schema on a remote Windows or UNIX Oracle Enterprise database. CM subsequently performs all database operations with that remote schema.

The client database can be:

- An Oracle-supplied Windows client installation.
- An Oracle-supplied Windows instant client installation.
- A full Oracle-supplied Windows installation.

**NOTE** For Oracle Instant Client on Windows, Dimensions CM requires the following packages:

- instantclient-basic-<platform>-<version>.zip
- instantclient-sqlplus-<platform>-<version>.zip

After you have set up your client Oracle installation:

- 1** Prepare the remote Oracle RDBMS:

- For a remote Windows Oracle, see below.
  - For a remote UNIX Oracle, see the *Installation Guide for UNIX*.
- 2 Set up a local Oracle Net Service Name on the remote Oracle database that you want the CM server to communicate with, see below.

### ***Preparing a Oracle Enterprise***

Preparing a remote instance is the same as preparing a local instance; however, when you install a CM server with an Oracle Enterprise database, you are prompted for the Oracle Net Service Name. This is the name that the local client uses to identify a specific remote Oracle databases for network operations.

### ***Setting Up a Local Oracle Net Service Name***

When you install a CM server with a remote Oracle Enterprise database you are prompted for the Oracle Net Service Name. This is the name that the local client uses to identify a specific remote Oracle databases for network operations.

On your local Windows machine define the Net Service Name of the remote Oracle database that you want the CM server to communicate with.

- 1 Start the Oracle Net Configuration Assistant:  
Start | Oracle <oracle\_home> | Configuration and Migration Tools | Net Configuration Assistant
- 2 Select **Local Net Service Name configuration**.
- 3 Select **Add**.
- 4 Enter the service name of the remote database you want the local database client to communicate with.
- 5 Select the **TCP** protocol.
- 6 Enter the remote database's host name.
- 7 Accept the standard port number (1521) or enter a different one.
- 8 Optionally test the connection to the remote database.



- 
- 9 Assign an Oracle net service name. This is the name that your local client database uses to identify the remote database.

Default: same SID as the Net Service Name. If the name is not unique enter a different net service name

- 10 Click **Next** and **Finish**.

## Preparing an SQL Server

### SQL Server Version

Your version of SQL Server must be compatible with Dimensions CM. For details, see [Support](#).

### SQL Server Collation Restrictions

The physical storage of character strings in Microsoft SQL Server Enterprise is controlled by collations. A collation specifies the bit patterns that represent each character and the rules by which characters are sorted and compared.

For a Dimensions CM for SQL Server Enterprise installation to succeed, the following restrictions apply to collations:

- The SQL Server instance must be configured to use mixed authentication mode.
- The default collation of the SQL Server instance must be case-insensitive (for example, `Latin1_General_CI_AS`).
- The server installer creates a database in the specified SQL Server instance. By default, the collation of the database is the same as the default collation of the SQL Server instance. Before the database is created you can specify a non-default collation. Both the SQL Server instance and the CM database must use case-insensitive collations. The CM server installer does not proceed if you specify a case-sensitive collation. If you plan to use a SQL Server database collation name with a collation designator other than `Latin1_General`, contact [Support](#) before proceeding.

## Preparing Local and Remote Nodes

### ***Setting Trustworthy Mode***

To successfully install a Dimensions CM schema into a SQL Server Enterprise database, the database should be in "trustworthy mode". For a local SQL Server Enterprise database, the Dimensions CM installer automatically sets trustworthy mode to 'true'.

For an upgrade or installation with a remote SQL Server Enterprise database, there is no installer support for setting trustworthy mode to 'on'.

#### **To check that trustworthy mode, set it to 'true':**

- 1 Open SQL Server Management Studio.
- 2 Connect to a SQL Server database instance.
- 3 In Object Explorer expand **Databases** and select the database to use.
- 4 Right-click and select Properties and then Options.
- 5 Under Miscellaneous, look for Trustworthy and verify that it is set to True.

#### **To change or modify trustworthy mode:**

- 1 Check there are no connections to the database.
- 2 Open the SQL Server Management Studio.
- 3 Connect to a SQL Server database instance.
- 4 In Object Explorer expand **Databases** and select the database to use.
- 5 Right-click and select **New Query**.
- 6 Enter the following text in the query window:  

```
alter database <dbname> set trustworthy on
```

  
where <dbname> is the name of the database.
- 7 On the toolbar click **Execute**.

---

## 8 Exit SQL Server Management Studio.

**NOTE** If you backup your database and then restore it into the same or a different database, by default trustworthy mode is set to 'off'.

### ***Local and Remote Node Prerequisites***

Check that both machines are in the same Windows domain and that there is a network user-id available that can be assigned to be the Dimensions CM system administrator, also known as dmsys (referred to here as <DOMAIN\DSA>). This user needs to be an operating system administrator user on the Dimensions CM server (the local node) but does not need to be an operating system administrator on the SQL Server database machine (the remote node).

### ***SQL Server Enterprise Roles***

Allocate the following SQL Server roles to the user performing the installation with SQL Server Enterprise:

- public
- sysadmin

You must also allocate the same roles to local administrator accounts as SQL Server Enterprise does not automatically give administrative rights.

### ***Remote SQL Server Prerequisites***

Before installing Dimensions CM, complete the SQL Server pre-installation steps, which includes the following:

- Create the database.
- Create the OpenText PulseUno user.
- 1 On the remote machine where the SQL Server database is installed, log in as the <DOMAIN\DMSYS> user.
- 2 Verify that <DOMAIN\DMSYS> has a login to connect to the SQL Server:
  - a Open SQL Server Management Studio and connect to a server.
  - b In Object Explorer expand Security | Logins.
  - c Verify that <DOMAIN\DSA> is listed.

- 3** Verify that <DOMAIN\DSA> has the appropriate SQL Server Roles (public and sysadmin) to perform the installation:
  - a** In Object Explorer expand Security | Server Roles.
  - b** Right-click sysadmin and select Properties.
  - c** In the Server Roles dialog click Add.
  - d** In the Select Logins dialog add <DOMAIN\DSA> as a member of the sysadmin role.

- 4** Copy these files from the DVD or the download folder:

```
db_preinstall\mssql\win32\mssql_pre_install.cmd  
db_preinstall\mssql\win32\pulse_mssql_pre_install.cmd
```

Copy the files to the <SQL Server Home>\binn folder on the remote database machine, for example:

```
C:\Program Files\Microsoft SQL Server\MSSQL.1\MSSQL\binn
```

- 5** Do the following:
  - a** Open a command prompt on the SQL Server database machine.
  - b** Navigate to the <SQL Server Home>\binn folder where you copied the files in a previous step.
  - c** Run this command:

```
mssql_pre_install.cmd <SQL Server instance>  
    <Dimensions database name to be created>  
    <Database files directory to be created>  
    <DOMAIN\DSA>  
    <PCMS_SYS SQL password>  
    <Database filesize to be allocated (MB)>  
    <Logfile size to be allocated (MB)>  
    <Collation of the database>  
    <Language of the database account>
```

Example 1: for the named instance NWB-VADYMK\DMSQL2K

```
mssql_pre_install NWB-VADYMK\DMSQL2K dim14 \  
C:\mssql\datafiles NWB-VADYMK\DMSSYS pcms_sys \  
30 15 Latin1_General_CI_AS us_english
```

Example 2: for the default instance (local)

```
mssql_pre_install (local) dim14 \  
C:\mssql\datafiles NWB-VADYMK\DMSSYS pcms_sys \  
30 15 Latin1_General_CI_AS us_english
```

---

## 6 From the same command prompt, run this command:

```
pulse_mssql_pre_install <SQL Server instance>  
<Dimensions Database name>  
<Path to the database files directory to be created>  
<DOMAIN\DSA>  
<PULSE SQL username>  
<PULSE SQL user password>  
<Database filesize to allocate (MB)>  
<Logfile size to allocate (MB)>  
<Collation of the database>  
<Language of the database account>
```

Example:

```
pulse_mssql_pre_install NWB-VADYMK\DMSQL2K dim14  
"C:\mssql\datafiles" NWB-VADYMK\DMSYS pulse pulse 30 15  
Latin1_General_CI_AS us_English
```

## Configuring a Local Server for Remote SQL

To perform database service operations, a Dimensions CM server requires access to an SQL Server database through an SQL Server client. The client can be:

- An SQL Server client
- SQL Server Enterprise

Dimensions CM performs all database operations with that remote schema utilizing ODBC connectivity using a Microsoft ODBC driver. To check the driver and SQL version compatibility, see the *Microsoft help*.

Dimensions CM for SQL Server Enterprise does not ship with any SQL-related modules or software and relies on the installed ODBC driver to manage and access its base databases.

The Dimensions CM for SQL Server Enterprise installer offers you the option of using an existing ODBC connection or creating a new one. When you perform a remote install, we recommend that you create the ODBC before installing.

### **Creating an ODBC Driver**

Set up an SQL Server client locally to perform operations between the local CM server and the SQL remote database. Create a local ODBC DSN that has the same name as the remote Dimensions CM database.

- 1 In Administrative Tools, open Data Sources (ODBC).
- 2 On the System DSN tab, click **Add**.
- 3 In the Create a New Data Source dialog box, select **ODBC Driver <version> for SQL Server** and click **Finish**.  
  
To check the driver and SQL version compatibility, see the *Microsoft help*.
- 4 In the Create a New Data Source to SQL Server dialog box, provide the following details, and click **Next**:
  - **Name**: Enter the name of the Dimensions CM database that is the source of the data.
  - **Description**: Enter a description of the data source.
  - **Server**: Select the SQL Server to connect to.
- 5 Accept the default option for verifying login authenticity, and click **Next**.
- 6 Select the option **Change the default database to**. Then select the database name from the list. Click **Next**.
- 7 Select the option **Change the language of SQL Server system messages to**. Then select **English** from the list.
- 8 Click **Finish**.
- 9 (Optional) Test the connection.
- 10 Perform the Dimensions CM installation as the user <DOMAIN\DSA>, for example: DOMAIN\dmsys

## SQL Server Enterprise Roles

Allocate the following SQL Server roles to the user performing the installation with SQL Server Enterprise:

- public
- sysadmin

You must also allocate the same roles to local administrator accounts, as SQL Server Enterprise no longer has a BUILTIN\Administrators Login to automatically give you administrative rights.

---

## Removing Oracle Registry Keys

If you are installing CM with SQL Server Enterprise on Windows, and Oracle was installed on the system at the time of the original Dimensions installation, before installing run `regedit` and remove the appropriate the key:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Serena\Dimensions\  
<version>\Install\INSTALL_OracleSid
```

## Oracle Multi-Byte Character Sets

### Oracle Database Character Set

When setting up an Oracle database for Dimensions CM, we recommend that you choose the AL32UTF8 Unicode UTF-8 multibyte character set (MBCS). But Dimensions CM automatically works with Oracle databases used with earlier versions of CM that have MBCS/ASCII character sets.

If you plan to use a character set for an Oracle installation other than AL32UTF8, consult Support before proceeding.

**IMPORTANT!** Dimensions RM supports the Oracle AL32UTF8 character set. All data entered be ASCII characters for Dimensions RM to display it correctly. If you intend using Dimensions RM to access data in a Dimensions CM AL32UTF8 database, that data must also be entered as ASCII. This is especially important for project, stream, and product names.

### Homogeneous Server-Client Environment

An Oracle database with an US7ASCII character set supports multi-byte character sets as follows:

- A homogeneous environment is used for MBCS. If the desktop client, and either the web client or Administration Console are used, the Tomcat server must run on a Windows machine with the same locale as the client machines.
- All machines that access the database must use the same locale. Data appears corrupt if it is read from:

- A client that is different to the one where the data was entered.
- A machine with a different locale.

## Preparing a PostgreSQL Database

**IMPORTANT!** Depending on the PostgreSQL distribution you installed, the installation paths may be different.

### Managing Large Objects

The LO extension is a pre-requisite and must be public. Run this PostgreSQL command:

```
alter extension lo set schema public;
```

### Preparing a Local PostgreSQL

To use a pre-installed local PostgreSQL database, configure it to enable local access via the local host name or IP address.

- 1 Modify the following file:

```
%POSTGRES_HOME%\data\pg10\pg_hba.conf
```

- 2 Add the following lines:

```
host all all <this hosts IPV6 address>/120 md5
host all all <this hosts IPV4 address>/24 md5
```

### Preparing a Remote PostgreSQL

To use a pre-installed remote PostgreSQL database, log in to the remote machine and configure it as follows.

- 1 Verify that the PostgreSQL server is listening on the correct network address. Open this file:

```
%POSTGRES_HOME%\data\pg10\postgresql.conf
```

Check the settings for the parameter `listen_addresses`.



- 
- 2 Modify the following file:

`%POSTGRESQL_HOME%\data\pg10\pg_hba.conf`

Add the following lines:

```
host all all <this hosts IPV6 address>/120 md5
host all all <this hosts IPV4 address>/24 md5
```

- 3 Verify that the `psql` utility is available on your path, for example:

```
SET PATH=%PATH%;%POSTGRESQL_HOME%\bin
```

Do not 'quote' the PostgreSQL installation path, even if it includes spaces.

- 4 If required, run `initdb` to create a PostgreSQL database cluster, for example:

```
initdb -U postgres -D C:\ProgramData\PostgreSQL\data
```

- 5 Run the following scripts to create the main database users and roles, in the following order:

```
db_preinstall\postgresql\win64\
  postgresql_pre_install.cmd
  pulse_postgresql_pre_install.cmd
```

Both scripts describe the mandatory parameters.

Example commands:

```
cmd /e:on /c postgres_pre_install.cmd /dbadmin postgres /
dbadmin_pwd postgres_password /dbname dim14 /datadir
c:\DATADIR /dbowner postgres
```

```
cmd /e:on /c pulse_postgres_pre_install.cmd /dbadmin
postgres /dbadmin_pwd postgres_password /dbname dim14
/pulse_user pulse
```

## Scaling and Performance Tuning

PostgreSQL ships with a basic configuration tuned for wide compatibility rather than performance, and the default parameters may be undersized for your system. See the following PostgreSQL web pages:

[Tuning](#)

[Resource consumption](#)

## High Availability and Load Balancing

PostgreSQL offers native capability for load balancing and fail over, see the [PostgreSQL documentation](#).

## Chapter 5

---

# Installing Dimensions CM

Installation Options	60
Running the Installer	61
Installing all Server Components	62
Installing a Windows Server Only	75
Installing an SSO Server and Smart Card	78
Installing a Windows Agent	80
Installing a Windows Client	82
Silently Installing Windows Agents and Clients	84
Installing Dimensions CM Make for Windows	91
Installing the Eclipse Integration	92
Installing Other Integrations	95

# Installation Options

Installation Option	Components	See
Server with all components	<ul style="list-style-type: none"> <li>■ Server core files</li> <li>■ Local or remote schema on a PostgreSQL, Oracle, or SQL database</li> <li>■ OpenText Common Tools</li> <li>■ Migration console</li> <li>■ Single Sign On (SSO) server</li> <li>■ Smart card authentication</li> <li>■ Deployment Automation (DA) server</li> <li>■ PulseUno and the Git and Vault servers</li> </ul>	<a href="#">page 62</a>
Server only	Server only (no schema)	<a href="#">page 75</a>
SSO	<ul style="list-style-type: none"> <li>■ New SSO server, with or without smart card, into an existing CM installation</li> <li>■ Connect a CM server to an existing SSO server with or without smart card</li> </ul>	<a href="#">page 78</a>
Agent	<ul style="list-style-type: none"> <li>■ Agent</li> <li>■ Deployment Automation agent</li> </ul>	<a href="#">page 80</a>
Client	<ul style="list-style-type: none"> <li>■ Desktop client</li> <li>■ Developer's toolkit</li> <li>■ SCC integration</li> <li>■ Administration command line interface</li> <li>■ Windows Explorer shell extension</li> <li>■ Visual Studio integration</li> <li>■ Visual Studio migration tool</li> <li>■ Merge tools</li> </ul>	<a href="#">page 82</a>
Dimensions Make	Dimensions Make for Windows	<a href="#">page 91</a>
Dimensions CM integrations	Dimensions CM integrations for Windows	<a href="#">page 95</a>

---

# Running the Installer

## Running the Installer from a DVD

**NOTE** If you are using Internet Explorer 8 check that it is running in compatibility view:

Tools | Compatibility View Settings | Display all Websites in Compatibility View

- 1 Log in as a user with local administrative privileges and insert the DVD into the drive. If the HTML installation front end does not automatically start, do one of the following:
  - Right-click the DVD icon and select **AutoPlay**.
  - Run the appropriate file from the DVD drive.
- 2 Select **Click here >>**.
- 3 Select the component you want to install.

## Running the Installer from a Download

- 1 Download the installation files from [Support](#). There are separate files for server, agent, and client.
- 2 Unzip the files.
- 3 Log in as a user with local administrative privileges.
- 4 Run the appropriate installer.

### **IMPORTANT!**

Check that the folder common was extracted to the same location as the installers.


# Installing all Server Components

## Remote Schema Requirements

Your environment may require a schema to be installed on a remote database rather than the local node. For example, users on a local node want to use a remotely administered database. To use a remote database, a client must be set up on the local node to perform database operations between the local server and the remote database. The client can be any of the following:

- SQL Server:
  - An SQL Server Enterprise client
  - A full SQL Server Enterprise installation
- Oracle RDBMS
  - An Oracle client
  - An Oracle instant client
  - A full Oracle Enterprise installation

Multiple database connectivity mechanisms are supported. The diagram below shows the connectivity supported by PostgreSQL, Oracle, and SQL server clients.



---

## Installing a Database Remotely on Another Platform

Oracle instances are installed and configured differently on Windows and UNIX. If you plan to install Dimensions CM on a Windows system and create an Oracle instance on a remote UNIX environment, before installing check that a `pcms_sys` Oracle user does not exist on the Windows client Oracle RDBMS.

## SSO and Smart Card Limitations

- The only smart card client reader supported is the Common Access Card (CAC), a United States Department of Defense (DoD) smart card issued as standard identification for logging in to DoD hosted software.
- Installing or configuring an SSO server requires specific Light Directory Access Protocol (LDAP) parameters. For details, see [page 28](#).
- See the SSO and smart card prerequisites on [page 28](#).

## Installing a Server with a PostgreSQL Database

- 1 Run the server installer (see [page 61](#)). Read and accept the license agreement.
- 2 For Database Type, select **PostgreSQL**.
- 3 Select a database option:
  - **Create new database installation.** Use the version of PostgreSQL included with the installer.
  - **Use existing local database installation.** Use an existing PostgreSQL database located on the local machine.
  - **Use existing remote database installation.** Use an existing PostgreSQL database located on a remote machine.
- 4 Select installation components:
  - **Single Sign On**

Installs or configures a connection to an SSO server. You can also configure smart card authentication.

- **Deployment Automation**

Installs a Deployment Automation server.

- **PulseUno**

Installs a PulseUno server (required) and its modules (optional):

- **Git server:** The server that PulseUno uses for Git repositories.
- **Vault server:** The server that PulseUno uses for the library of software packages.

For details about separating the database upgrade or migration operations from the server installation, contact [Support](#).

**5** Accept the default installation folder or choose a different one.

**6** If you are installing an SSO server, select one of the following:

- **New:** Install a new SSO server.
- **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).

**7** If you are installing an SSO server and smart card, configure the connection:

- **Existing SSO server:** Specify the SSO server's host name and port. Optionally select a secure HTTPS connection.
- **New SSO server without smart card:**

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Defaults:

- Port: 389
- Search Filter:  
`(&(objectClass=user)(sAMAccountName={0}))`
- **New SSO server with smart card:**
  - To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.



---

Default port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

`(&(objectClass=user)(sAMAccountName={0}))`.

After completing the installation, manually configure the smart card trusted certificate authorities. For details, see [page 105](#).

**8 Select Dimensions server components and schema.**

**9 Select a licensing option:**

- **Specify License Server.**

If the AutoPass License Server (APLS) is running on a remote machine, enter the URL of the remote machine.

If APLS is running on the same machine as the Dimensions CM server, accept the following localhost URL:

**`https://localhost:5814/autopass`**

For details about configuring Dimensions CM to use APLS, see the [Dimensions CM online help](#).

- **Install a 30-day evaluation license.**

**10 Enter the PostgreSQL installation or connection details:**

- **New PostgreSQL installation:**

- a Accept the default installation folder or select a different one.
- b Accept the default data directory or select a different one.
- c Enter the name and password of the PostgreSQL SuperUser.
- d Accept the default port number or enter a different one.
- e Click **Next** and then enter the Dimensions CM database name and the DB Owner credentials.

- **Existing local PostgreSQL installation:**

Select a local installation from the list, or click **Manual Entry** and enter the PostgreSQL details:

- Home and data directories.

- Database name and port number.
  - SuperUser name and password.
  - **Existing remote PostgreSQL installation:**
    - a** Enter the server host name and port number.
    - b** Enter the Dimensions CM database name.
    - c** Enter the name and password of the PostgreSQL SuperUser.
    - d** (Optional) Check the connection to the database.
- 11** Enter the password for the PCMS\_SYS schema. This schema stores system data for the Dimensions CM installation. Default: pcms\_sys
- 12** Select a demo process model. For details, see [page 23](#).
- 13** For process model options, specify the following:
- a** Enter the operating system ID of the tool manager for the demo process model. Default: dmsys
  - b** Enter the credentials for the work and deployment areas:
    - Area Owner ID  
Accept the default (dmsys) or enter a login ID. This user is set by default as the system administrator login ID.
    - Password  
Enter the password for the area owner.
  - c** Accept the default folder for the demo process model areas or select a different one.
- After completing the installation, you must assign operating system user accounts to the users in the sample process model.
- 14** Enter the OS login account name and password for the Dimensions CM system administrator. Default login: dmsys
- 15** If you are installing a Deployment Automation server:
- a** Accept the default installation folder or choose a different one.
  - b** (Optional if DA is already installed) Select **Use existing settings**.
  - c** (Optional) Select **Skip database creation**.

- 
- d Specify the port number for Deployment Automation agents to make Java Message Service (JMS) connections to the server.  
Default: 7918
  - e Select **Agent Mutual Authentication** if you want Deployment Automation to use agent authentication when connecting to the server.
  - f Specify a username and password for a new Deployment Automation database account to be created.

For details about installing and using DA, see [Support](#).

- 16 (Optional) Enter the host name of an email server so that CM can send emails to users, for example, when items are actioned. For details about configuring emails, see the *Administration Guide*.
- 17 If you are not installing the PulseUno Git and Vault modules, choose whether to configure the Git and Vault server connection:
  - To configure the connection, specify the host name and port number for the Git/Vault server. Optionally select the HTTPS option to enable HTTPS.
  - To skip configuring the connection, select **Do not configure PulseUno for a remote Git/Vault server**.
- 18 Accept the default port number for the Tomcat server (8080) or enter a different one if it is in use. Some software is hard-coded to port 8080 and cannot be reassigned (see [page 25](#)).
- 19 Click **Install**. When the installation is complete, click **Finish**.

## Installing a Server with an Oracle Database

- 1 Run the server installer (see [page 61](#)). Read and accept the license agreement.
- 2 For Database Type, select **Oracle**.
- 3 Select a database location:
  - **Local:** Use an Oracle database located on the local machine.
  - **Remote:** Use an Oracle database located on a remote machine.
- 4 Select installation components:

- **Single Sign On**

Installs or configures a connection to an SSO server. You can also configure smart card authentication.

- **Deployment Automation**

Installs a Deployment Automation server.

**IMPORTANT!** You must not install DA into a Serena-Supplied Runtime.

- **PulseUno**

Installs a PulseUno server (required) and its modules (optional):

- **Git server:** The server that PulseUno uses for Git repositories.
- **Vault server:** The server that PulseUno uses for the library of software packages.

For details about separating the database upgrade, or migration operations, from the server installation, contact [Support](#).

**5** Accept the default installation folder or choose a different one.

**6** If you are installing an SSO server, select one of the following:

- **New:** Install a new SSO server.
- **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).

**7** If you are installing an SSO server and smart card, configure the connection:

- **Existing SSO server:** Specify the SSO server's host name and port. Optionally select a secure HTTPS connection.
- **New SSO server without smart card:**

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Defaults:

- Port: 389
- Search Filter:  
`(&(objectClass=user)(sAMAccountName={0}))`

---

- **New SSO server with smart card:**

- To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.

Default port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

`(&(objectClass=user)(sAMAccountName={0}))`.

After completing the installation, manually configure the smart card trusted certificate authorities. For details, see [page 105](#).

**8 Select Dimensions server components and schema.**

**9 Select a licensing option:**

- **Specify License Server.**

If the AutoPass License Server (APLS) is running on a remote machine, enter the URL of the remote machine.

If APLS is running on the same machine as the Dimensions CM server, accept the following localhost URL:

**`https://localhost:5814/autopass`**

For details about configuring Dimensions CM to use APLS, see the [Dimensions CM online help](#).

- **Install a 30-day evaluation license.**

**10 Select a local or remote Oracle installation from the list, or click **Manual Entry** and enter the Oracle SID and Oracle Home.**

For a remote Oracle, specify:

- **Oracle Home:** the location of your local Oracle client to manage communication with the remote database.
- **Oracle SID:** the Net Service Name by which your client installation knows the remote database.

For a container database, click **PDB Details** and specify the **Oracle Home** and the **PDB Name**.

- 11** Enter the user and password for the Oracle administration account.  
Defaults:
  - User ID: system
  - Password: manager
- 12** Enter the password for the PCMS\_SYS schema for the Oracle instance. Default: pcms\_sys
- 13** Select a demo process model. For details, see [page 23](#).
- 14** For process model options, specify the following:
  - a** Enter the operating system ID of the tool manager for the demo process model. Default: dmsys
  - b** Enter the credentials for the work and deployment areas:
    - Area Owner ID  
Accept the default (dmsys) or enter a login ID. This user is set by default as the system administrator login ID.
    - Password  
Enter the password for the area owner.
  - c** Accept the default folder for the demo process model areas or select a different one.

After the installation you must assign operating system user accounts to the users in the sample process model.
- 15** Enter the OS account name and password for the Dimensions CM system administrator. Default: dmsys
- 16** If you are installing a Deployment Automation server:
  - a** Accept the default installation folder or choose a different one.
  - b** (Optional if DA is already installed) Select **Use existing settings**.
  - c** (Optional) Select **Skip database creation**.
  - d** Specify the port number for Deployment Automation agents to make Java Message Service (JMS) connections to the server.  
Default: 7918

- 
- e Select **Agent Mutual Authentication** if you want Deployment Automation to use agent authentication when connecting to the server.
  - f Specify a username and password for a new Deployment Automation database account to be created.

For details about installing and using DA, see [Support](#).

- 17 (Optional) Enter the host name of an email server so that CM can send emails to users, for example, when items are actioned. For details about configuring emails, see the *Administration Guide*.
- 18 If you are not installing the PulseUno Git and Vault modules, choose whether to configure the Git and Vault server connection:
  - To configure the connection, specify the host name and port number for the Git/Vault server. Optionally select the HTTPS option to enable HTTPS.
  - To skip configuring the connection, select **Do not configure PulseUno for a remote Git/Vault server**.
- 19 Accept the default port number for the Tomcat server (8080) or enter a different one if it is in use. Some software is hard-coded to port 8080 and cannot be reassigned (see [page 25](#)).
- 20 Click **Install**. When the installation is complete, click **Finish**.

## Installing a Server with an SQL Database

- 1 Run the server installer (see [page 61](#)). Read and accept the license agreement.
- 2 For Database Type, select **SQL Server**.
- 3 Choose an ODBC connection:
  - **Existing:** Use an existing ODBC connection to a database.
  - **New:** Create a new ODBC connection to a database.
- 4 Select a database location:
  - **Local:** Use an SQL database located on the local machine.
  - **Remote:** Use an SQL database located on a remote machine.

If you are installing a CM server into a remote SQL Server, you must use an existing and preconfigured ODBC. Creating a new ODBC as part of the installation does not work.

**5** Select installation components:

- **Single Sign On**

Installs or configures a connection to an SSO server. You can also configure smart card authentication.

- **Deployment Automation Server**

Installs a Deployment Automation server.

- **PulseUno**

Installs a PulseUno server (required) and its modules (optional):

- **Git server:** The server that PulseUno uses for Git repositories.
- **Vault server:** The server that PulseUno uses for the library of software packages.

For details about separating the database upgrade, or migration operations, from the server installation, contact [Support](#).

**6** Accept the default installation folder or choose a different one.

**7** If you are installing an SSO server, select one of the following:

- **New:** Install a new SSO server.
- **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).

**8** If you are installing an SSO server and smart card, configure the connection:

- **Existing SSO server:** Specify the SSO server's host name and port. Optionally select a secure HTTPS connection.
- **New SSO server without smart card:**

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Defaults:

- Port: 389



- 
- Search Filter:  
((&(objectClass=user)(sAMAccountName={0})))

- **New SSO server with smart card:**

- To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.

Default port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

((&(objectClass=user)(sAMAccountName={0}))) .

After completing the installation, manually configure the smart card trusted certificate authorities. For details, see [page 105](#).

**9** For components, select **Dimensions server components and schema**.

**10** Select a licensing option:

- **Specify License Server.**

If the AutoPass License Server (APLS) is running on a remote machine, enter the URL of the remote machine.

If APLS is running on the same machine as the Dimensions CM server, accept the following localhost URL:

**<https://localhost:5814/autopass>**

For details about configuring Dimensions CM to use APLS, see the [Dimensions CM online help](#).

- **Install a 30-day evaluation license.**

**11** Configure an ODBC connection:

- **Existing ODBC connection:**

Enter the database name and ODBC DSN for an existing connection.

- **New ODBC connection:**

- a** Select the local or remote SQL Server instance you want to create an ODBC connection to.  
  
Default: local or MSSQLSERVER depending on whether you are running SQL Server Enterprise.
  - b** Enter the database name and ODBC DSN for the new connection or accept the default values. These values are used by the Dimensions CM schema. The DSN is an ODBC data source that stores information about how to connect to the database.
  - c** Specify the folder containing the SQL Server installation.
  - d** Specify the folder where to create the SQL database.
  - e** Specify the disk space to be allocated to CM data and log files.
- 12** Enter the password for the PCMS\_SYS schema for the CM schema.  
Default: pcms\_sys
- 13** Select a demo process model. For details, see [page 23](#).
- 14** For process model options, specify the following:
  - a** Enter the operating system ID of the tool manager for the demo process model. Default: dmsys
  - b** Enter the credentials for the work and deployment areas:
    - Area Owner ID  
  
Accept the default (dmsys) or enter a login ID. This user is set by default as the system administrator login ID.
    - Password  
  
Enter the password for the area owner.
  - c** Accept the default folder for the demo process model areas or select a different one.

After the installation you must assign operating system accounts to the users in the sample process model.
- 15** Enter the OS account name and password for the Dimensions CM system administrator. Default: dmsys
- 16** If you are installing a Deployment Automation server:

- 
- a Accept the default installation folder or choose a different one.
  - b (Optional if DA is already installed) Select **Use existing settings**.
  - c (Optional) Select **Skip database creation**.
  - d Specify the port number for Deployment Automation agents to make Java Message Service (JMS) connections to the server.  
Default: 7918
  - e Select **Agent Mutual Authentication** if you want Deployment Automation to use agent authentication when connecting to the server.
  - f Specify a username and password for a new Deployment Automation database account to be created.

For details about installing and using DA, see [Support](#).

- 17 (Optional) Enter the host name of an email server so that CM can send emails to users. For details about configuring emails, see the *Administration Guide*.
- 18 If you are not installing the PulseUno Git and Vault modules, choose whether to configure the Git and Vault server connection:
  - To configure the connection, specify the host name and port number for the Git/Vault server. Optionally select the HTTPS option to enable HTTPS.
  - To skip configuring the connection, select **Do not configure PulseUno for a remote Git/Vault server**.
- 19 Accept the default port number for the Tomcat server (8080) or enter a different one if it is in use. Some software is hard-coded to port 8080 and cannot be reassigned (see [page 25](#)).
- 20 Click **Install**. When the installation is complete, click **Finish**.

## Installing a Windows Server Only


### Overview

Your environment may require a local Windows server without an Oracle schema, for example:

- There is already a local Oracle Enterprise with the schema. This is a binary only install.
- You do not require any of the demo process models and are going to import a process model file that was exported from another database.
- You want to install a local server, with a local Oracle Enterprise RDBMS but without a schema, to communicate with a remote Windows or UNIX database.

A locally installed server is similar to an agent installation as it provides listener services and the `dmcli` command client. Common Tools are also installed. You may want to do this:

- When the users on the local node do not have operating-system accounts on the remote database server.
- To balance loads across both the local node and the remote database server node, as illustrated below.



A remote database server is an RDBMS with a Dimensions CM schema installed. To enable network connections between the nodes the remote database server must be running the TNS listener. You also need to set up an Oracle Net Service Name on the local node to access the Oracle database, see [page 48](#).

## Installing a Server Only

- 1 Run the server installer (see [page 61](#)). Read and accept the license agreement.

- 
- 2 For Database Type, select **Oracle**.
  - 3 Select a database location:
    - **Local:** Use a database located on the local machine.
    - **Remote:** Use a database located on a remote machine.
  - 4 Select **Dimensions Server** and deselect all other installation components.
  - 5 Accept the default installation folder or choose a different one.
  - 6 For database schema options, select **Dimensions server components only**.
  - 7 Select a licensing option:
    - **Specify License Server.**

If the AutoPass License Server (APLS) is running on a remote machine, enter the URL of the remote machine.

If APLS is running on the same machine as the Dimensions CM server, accept the following localhost URL:

**`https://localhost:5814/autopass`**

For details about configuring Dimensions CM to use APLS, see the [Dimensions CM online help](#).
    - **Install a 30-day evaluation license.**
  - 8 When you are prompted to select an Oracle installation, click **Next**.
  - 9 Enter the OS account name and password for the CM system administrator. Default: dmsys
  - 10 (Optional) Enter the host name of your email server.
  - 11 Accept the default port number for the Tomcat server (8080) or enter a different one if it is in use. Some software is hard-coded to port 8080 and cannot be reassigned (see [page 25](#)).
  - 12 Click **Install**. When the installation is complete, click **Finish**.

# Installing an SSO Server and Smart Card

## SSO and Smart Card Limitations and Requirements

- The only smart card client reader supported is the Common Access Card (CAC), a United States Department of Defense (DoD) smart card issued as standard identification for logging in to DoD hosted software.
- Installing or configuring an SSO server requires specific Light Directory Access Protocol (LDAP) parameters. For details, see [page 28](#).
- See the SSO and smart card prerequisites on [page 28](#).

## Installing SSO and Smart Card

- 1 Run the server installer (see [page 61](#)). Read and accept the license agreement.
- 2 Select **Modify** to add features to an existing CM installation.
- 3 Select these installation options:
  - Single Sign On
  - (Optional) Smart Card Setup
- 4 Select an SSO server installation option:
  - **New:** Install a new SSO server.
  - **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).
- 5 Do one of the following:
  - Existing SSO server:** Specify the SSO server's host name and port and optionally select a secure HTTPS connection.

### **New SSO server without smart card:**

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

---

Defaults:

- Port: 389
- Search Filter: (&(objectClass=user)(sAMAccountName={0}))

### **New SSO server with smart card:**

- To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.

Defaults port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

(&(objectClass=user)(sAMAccountName={0})).

- 6** Click **Install**. When the installation is complete, click **Finish**.
- 7** Manually configure the smart card trusted certificate authorities. For details, see [page 105](#).

## **Fixing Demo Certificate Mismatches**

**NOTE** Only applicable if you are using demo certificates.

Upgrading an 12.x server (without SSO) to the latest 14.x version and then enabling SSO with the demo certificates causes a mismatch of the jks and pem files. You need to manually restore the certificates on the latest server version, and restart Tomcat:

- 1** Stop the Tomcat service.

- 2** Rename this file:

```
..\common\tomcat\<tomcat-  
version>\alfssogatekeeper\conf\truststore.jks
```

Replace it with a file called truststore.jks.14.x.x in the same folder, where 14.x.x is the upgraded Dimensions CM version.

- 3** Rename this file:

```
c:\Program Files\OpenText\Dimensions  
<version>\cm\dfs\sts.pem
```

Replace it with a file called `sts.pem.14.x.x` in the same folder, where `14.x.x` is the upgraded Dimensions CM version.

- 4 Restart the Tomcat service.

## Installing a Windows Agent

### Installing an Agent

- 1 Run the agent installer (see [page 61](#)). Read and accept the license agreement.
- 2 (Optional) Select the Deployment Automation agent feature.
- 3 Accept the default installation folder or select a different one.
- 4 Enter the host name and port number of the server that provides auto update install packages.
- 5 To configure the installation of a Deployment Automation agent:
  - Specify the name of a DA agent process.
  - (Optional) Select **Server Mutual Authentication** if you want the agent to use mutual authentication with SSL when connecting to the Deployment Automation server.
  - (Optional) Connect to an agent relay instead of directly to the Deployment Automation server. Specify the following parameters for the agent relay:
    - Host name or address. Default: `localhost`
    - Communication port. Default: `7916`
    - HTTP proxy port: Default: `20080`

If you are connecting directly to a Deployment Automation server, specify:

- The host name or address of the server.
- The Java Message Service (JMS) communication port. Default: `7918`

For details about installing and using DA, see [Support](#).



- 
- 6 Click **Install**. When the installation is complete click **Finish**.

## Checking the Agent Installation

### *Installation Logs*

Check the installation logs before running any tests:

%DM\_ROOT%\InstallTemp

### *Agent Acceptance Tests*

**NOTE** To perform these tests you require access to a server.

- 1 As a user with local administrative privileges open Windows Services.
- 2 Check that the Dimensions CM Listener Service has the Status Started and Startup is set to Automatic.

If the listener service fails to start automatically, start it manually after the RDBMS database service has started.

- 3 Open the Windows task manager and check for the following Dimensions CM processes:

dimensions\_service.exe  
dm1snr.exe  
dmpool.exe

- 4 At a command prompt enter `dmcli` and log in to CM. The output should be a Dimensions CM banner and copyright message followed by a `Dimensions>` prompt.
- 5 Enter `exit`.

## Starting the Listener

By default the agent listener service is owned by the user with local administrative rights who installed Dimensions CM. You change the owner of the Dimensions system administrator.

- 1 Log in as a user with local Windows administrative rights and open Services.

- 2 Shut down the Dimensions CM Listener Service.
- 3 Log out as the user with local Windows administrative rights and log back in as the Dimensions system administrator.
- 4 Navigate to:  
  
`%DM_ROOT%\dfs`
- 5 Edit the file `listener.dat` and add the following entries:  
  
`-user <DSA_username>`  
`-restricted_mode`  
  
where `<DSA_Username>` is the Dimensions system administrator that runs the listener on the agent.
- 6 Restart the Dimensions CM Listener Service service.

#### NOTES

- When running an agent in restricted mode, area and remote node authentication credentials are not used. Files in a remote area are owned by the user running the `dmpool` process regardless of which user-id is set for the area or userid specified in Remote Node Authentication.
- Edit the Dimensions Listener Service so that it starts as the chosen non-administrator user.

## Installing a Windows Client

### Overview

You can install CM Windows clients:

- On a Windows machine that communicates with a Windows or UNIX server on the network.
- On the same Windows node as the server.
  - The server must be the same version as the client.
  - Install the server first. The client installer sets the target folder to the existing Dimensions CM server home folder.

---

## IMPORTANT!

- If you are installing on a 64-bit machine you must install the client with 64-bit Common Tools.
- Common Tools are not required for the 32-bit installer.

## Installing a Client

- 1 Run the client installer (see [page 61](#)). Read and accept the license agreement.
- 2 Accept the default installation folder or choose a different one.
- 3 From the Setup Type page choose **Custom**.
- 4 On the Custom Setup page select the features you want to install.

### NOTES

- If Microsoft Visual Studio is installed on the same machine, you can optionally install the Visual Studio integration.
  - Araxis Merge is installed by default however you can deselect this option. You can also optionally install the File Merge Tool.
  - Windows Shell Explorer Extension enables you to launch the Dimensions CM Synchronize Wizard from Windows Explorer. For details, see the online help.
  - Visual Studio Migration Tool does not require Visual Studio to be pre-installed. However, it does require Microsoft .NET Framework 3.5 or later.
- 5 (Optional) Specify the CM server connection details:
    - Server Hostname: The host name of a local or remote CM server.
    - Database Name: The database name on the server.
    - Database Connection: The database connection string.
    - Port Number: Accept the default port number for the Tomcat server (8080) or enter a different one if it is in use. Some software is hard coded to port 8080 and cannot be reassigned (see [page 25](#)).

**NOTE:** You can also specify this information the first time you connect to a CM server.

- 6 Enter the host name and port number of the server that provides auto update install packages.
- 7 Click **Install**. When the installation is complete click **Finish**. When you are prompted to restart the machine click **Yes**.

## Checking the Client Installation

**NOTE** To perform these tests, you need access to a server.

### *Checking the Command Client*

- 1 Do one of the following:
  - At a command prompt, enter `dmcli`.
  - Go to Start | Dimensions CM <version> | Command Client
- 2 Log in to Dimensions CM. If the login is successful, the CM prompt appears:  
  
`Dimensions>`

### *Checking the Desktop Client*

- 1 Go to Start | Dimensions CM <version> | Desktop Client
- 2 Log in to CM. If the login is successful, the desktop client opens.

## Silently Installing Windows Agents and Clients

You can invoke the agent or client installers with specific command-line parameters and use them on other Windows nodes to perform unattended cloned installations, known as "silent installations".

## Silently Installing OpenText Common Tools

**NOTE** The client installer requires a Java Runtime Environment (JRE) to be present.

- 1 Log in as a user with local administrative privileges.

- 
- 2 Create a folder called **common** in the location for the silent installer files.
  - 3 Navigate to where the CM installer files are located and copy the **common** folder and its contents. Copy to the **common** folder in the silent installer location.
  - 4 Open a command prompt and navigate to the **common** folder in the silent installer location.
  - 5 Run this command:

```
setupOpenTextCommonTools_win64.exe -silent -P  
installLocation="<Common Tools install location>" -  
V IS_DESTINATION="<Common Tools install  
destination>" -V JRE_ONLY=TRUE
```

For example:

```
setupOpenTextCommonTools_win64.exe -silent -P  
installLocation="C:\Program Files\OpenText\common"  
-V IS_DESTINATION="C:\Program  
Files\OpenText\common" -V JRE_ONLY=TRUE
```

**IMPORTANT!** The installation folder names must not include a trailing backslash (\). If they do, the double-quote are "escaped" and -V IS\_DESTINATION="C:\Program is appended to the folder name that the installer attempts to use, causing the installation to fail.

## Silently Installing Clients

- 1 Log in as a user with local administrative privileges.
- 2 Navigate to the CM installer files and copy this file (located at the same level as the "common" folder):  
  
`Dimensions_CM_Clients_<version>.exe`
- 3 Copy the file to the folder you are using for the client silent installer files (at same level as the "common" folder).
- 4 Open a command prompt and navigate to the silent installer folder.
- 5 Run one of these commands:
  - *Full installation with default settings*

**NOTE:** The Visual Studio integration is installed only if Visual Studio is detected.

```
"Dimensions_CM_Clients_<version>.exe" /s /v" /qn /log <log_dir>
    INSTALLDIR=<installation_dir>"
```

For example:

```
"Dimensions_CM_Clients_<version>.exe" /s /v" /qn /log
    \"C:\temp\install.log\"
    INSTALLDIR=\"C:\Program Files\OpenText\Dimensions
    <version>\CM\""
```

The installer automatically restarts Windows. To restart Windows at a specific time add the REBOOT parameter:

```
"Dimensions_CM_Clients_<version>" /s /v" /qn /log
    \"C:\temp\install.log\"
    INSTALLDIR=\"C:\Program Files\OpenText\Dimensions
    <version>\CM\" REBOOT=ReallySuppress"
```

- *Full installation with custom settings*

Enables you to specify clients. The Visual Studio for Dimensions integration must be specified last:

```
"Dimensions_CM_Clients_<version>.exe" /s /v"/qn /log <log_dir>
    INSTALLDIR=<installation_dir>
    DM_COMPUTER_NAME=<local_host_id>
    DM_SERVER_HOST_NAME=<Dimensions CM_server_host_id>
    DM_DB_NAME=<database_name on Dimensions CM_server>
    DM_DB_CONN=<database_connection_to
    _Dimensions CM_server_database> PORTNUMBER=<port_no>
    ADDLOCAL=<clients_spec> REBOOT=<reboot_param>"
```

For example:

```
"Dimensions_CM_Clients_<version>.exe" /s /v"/qn /log
    \"C:\temp\install.log\" INSTALLDIR=\"C:\Program
    Files\OpenText\Dimensions <version>\CM\"
    DM_COMPUTER_NAME=\"idd-vmbigxp2\" DM_SERVER_HOSTNAME=\"prod-
    server\" DM_DBNAME=\"cm_typical\" DM_DB_CONN=\"dim14\"
    PORTNUMBER=\"8080\"
    ADDLOCAL=AdminTools,CMShellExtension,Configuration_Files,
    DesktopClient"
```

**NOTES:**

- See below for the full list of silent install command parameters.
- If you do not specify an installation folder, the default is:  
C:\Program Files\OpenText\Dimensions <version>\CM

- DM\_COMPUTER\_NAME specifies the host-id of the local client machine.
- DM\_SERVER\_HOSTNAME specifies the host-id of the server.
- DM\_SERVER\_HOSTNAME, DM\_DB\_NAME, and DM\_DB\_CONN are used to prepopulate the client login dialog boxes.

**6** Check the log file to confirm that the clients have successfully installed.

### ***Silent Install Command Parameters***

<b>Parameter</b>	<b>Description</b>
/s	Uses silent mode during the installation.
/v	Allows the exe file to pass the parameters listed to the embedded msi file.
/qn	Specifies that silent mode is used. You can initially run the command without this parameter to check for any mistakes in your command.
/log	Specifies the log file to be created. Any folder specified must already exist. You should inspect this log after installation to confirm that the clients installed successfully.
INSTALLDIR	Specifies the folder in which to install the clients. Must end with the sub-folder CM\. <ul style="list-style-type: none"> <li>■ The folder specification should include a trailing backslash (\).</li> <li>■ For upgrades you must specify the existing installation folder.</li> </ul>
DM_COMPUTERNAME	Specifies the host-id of the computer on which the clients are installed.
DM_SERVER_HOSTNAME	Specifies the host-id of the computer on which the server is located.
DM_DB_NAME	Specifies the server database to be used by the clients (for example cm_typical)
DM_DB_CONN	Specifies the database connection-id to be used by the clients (for example dim14).
PORTNUMBER	Specifies the port number to be used by the OpenText Common Tools. Default: 8080

Parameter	Description
ADDLOCAL	<p>Lists the clients to be installed. If you reduce the list to limit functionality you may receive an error indicating that some required DLLs are not found. To resolve this issue modify the ADDLOCAL to include the required components, for example:</p> <pre>ADDLOCAL="Configuration_Files,PC_Client,DesktopClient,Project_Merge"</pre> <ul style="list-style-type: none"> <li>■ <b>Required</b> (Mandatory) Core configuration, message, and binary files.</li> <li>■ <b>AdminTools</b> The parent feature of SCC_Integration, VsMigration, and Dmpmcli. This parameter, and each child feature that you want to install, must be specified. For example: <pre>ADDLOCAL=\ "AdminTools, SCC_Integration,VsMigration,Dmpmcli\ "</pre></li> <li>■ <b>CMShellExtension</b> Windows Explorer shell extension. For Windows 64-bit add CMShellExtension_64Bit (see <a href="#">page 90</a>).</li> <li>■ <b>Configuration_Files</b> (Mandatory) Configuration files required by the ADDLOCAL components.</li> <li>■ <b>DesktopClient</b> The Dimensions desktop client (pcwin.exe).</li> <li>■ <b>DesktopShortcuts</b> Desktop shortcuts for the web client and OpenText PulseUno only.</li> <li>■ <b>DesktopClientShortcut</b> Desktop shortcut for the desktop client only.</li> <li>■ <b>Developers_Toolkit</b> The Developer's Toolkit.</li> <li>■ <b>Dmpmcli</b> Dimensions CM process modeling scripting interface.</li> </ul>



Parameter	Description
ADDLOCAL	<ul style="list-style-type: none"> <li>■ ISScript Script files internal to the installer.</li> <li>■ Make Dimensions CM Make.</li> <li>■ Araxis_Merge Araxis Merge tool only.</li> <li>■ Serena_Merge File Merge Tool only.</li> <li>■ PCClientServerFiles Copies server files required by the desktop client.</li> <li>■ Project_Merge Project Merge Tool.</li> <li>■ SCC_Integration The Dimensions SCC integration.</li> <li>■ VSIP Visual Studio integration. Must be specified last in the ADDLOCAL list.</li> <li>■ VsMigration Visual Studio migration tool.</li> <li>■ The following parameters are also mandatory: Toolkit_Shared_Lockable Transfer_Common_Files</li> </ul>
REINSTALL	For upgrades, specifies existing clients to be upgraded. Use ADDLOCAL to add clients during an upgrade.
REBOOT	"REBOOT=ReallySuppress" prevents an automatic restart at the end of the installation. However, to use the clients a restart is required.

## Silently Installing the Shell Extension on 64-bit Windows

The shell extension on Windows 64-bit is a separate installer that must be run at the end of the client installation. For silent installations, this is a manual procedure.

Adding CMShellExtension\_64Bit to the ADDLOCAL property copies the required files to the DMR00T\cmShell64 folder. You can launch the extension installer silently after the client installation has successfully completed using this command:

```
msiexec /qn /i  
    "[DMR00T]\cmShell64\Serena_Dimensions_Shell_Explorer_  
    64-bit.msi" INSTALLDIR="[DMR00T]"
```

If you are upgrading the client, uninstall the current cmshell64 before installing the new one:

- CM 14.1 only:  

```
uninstall {A8959131-E26B-4A4D-BB9D-2FDF11243921} "64-  
    bit Dimensions Shell Integration"
```
- All other versions of CM:  

```
uninstall {EC683EBB-5AD5-4F05-B626-F3A0B2F37636} "64-  
    bit Dimensions Shell Integration"
```

## Silently Installing an Agent

**NOTE** You do not need to pre-install the OpenText Common Tools.

- 1 As a user with local administrative privileges, navigate to the CM installer files and copy this file:

```
Dimensions_CM_Agents_<version>.exe
```

- 2 Copy the file to the folder with the agent silent installer files.
- 3 In a command prompt, go to the agent installer folder.
- 4 Run this command:

```
Dimensions_CM_Agents_<version>.exe" /s /v" /qn /log  
    <log_dir> INSTALLDIR=<installation_dir>"
```

---

For example:

```
"Dimensions_CM_Agents_<version>.exe" /s /v" /qn /log  
  \"C:\\temp\\install.log\" INSTALLDIR=\"C:\\Program  
  Files\\OpenText\\Dimensions <version>\\CM\""
```

# Installing Dimensions CM Make for Windows

## Introduction

Some of the Dimensions CM and ADG executables and associated libraries are derived from source code covered by the GNU GENERAL PUBLIC LICENSE and the GNU LIBRARY GENERAL PUBLIC LICENSE.

File	UNIX and Windows	UNIX Only	Windows Only
adg	Y		
dm_make	Y		
dm_nmake			Y
libmcx.so		Y	
mcx.dll			Y

To have a working Dimensions CM Make and ADG system you need to download the executables, libraries, "mini" installation scripts, and documentation (see below).

As a condition of the GNU GENERAL PUBLIC LICENSE and the GNU LIBRARY GENERAL PUBLIC LICENSE, source code for the above discussed executable and library files is also available. For details, see the *Dimensions CM Make Guide*.

## Downloading the Installer

To download the installer, contact [Support](#).

**IMPORTANT!** You can install only the 64-bit version if you have 64-bit CM server installed.

## Pre-Installation Requirements

- Dimensions CM server or client.
- Windows 64-bit requires a Dimensions CM client.

## Installing Make

- 1 As a user with administrative privileges, run the installer.
- 2 Read and accept the license agreement.
- 3 Click **Install**. When the installation is complete, click **Finish**.

## Installing the Eclipse Integration

Dimensions CM clients are not required to install the Eclipse integration.

For details about setting up and using the integration, see the [Dimensions CM online help](#).

## Installing the Integration from a Server

You can install the Eclipse integration from an update site hosted by the Dimensions CM server. The Tomcat `eclipse.war` file is added as part of the Dimensions CM server install.

You can use the same method to install *Appcelerator Titanium Studio* into Eclipse.

### To install the Eclipse integration from a server:

- 1 In Eclipse, go to **Help** > **Install New Software**. The Available Software dialog box opens.
- 2 In the **Work with** box, enter the update site URL:  
`http(s)://<host>:<port>/eclipse`  
where <host> and <port> point to the Tomcat installation.

---

**CAUTION:** For security reasons, Eclipse 2023 and later doesn't allow access to external upload sites that use HTTP protocol. To use an HTTP URL, add the following property as the last line to the `eclipse.ini` file in the Eclipse installation folder:

`-Dp2.httpRule=allow`

- 3 Select **Dimensions Eclipse Interface** and click **Next**.

**NOTE:** You may need to clear the Group by Category option to display the Dimensions Eclipse integration.

- 4 On the Install Details screen, click **Next**.
- 5 Accept the terms of the license agreement and click **Finish**.
- 6 After the software has been installed, restart Eclipse.

## Manually Installing the Integration

### *Pre-Installation Tasks*

Manually uninstall the previous version of the integration:

- 1 Shut down Eclipse.
- 2 Uninstall the existing integration.
- 3 Delete the following folder:

`%DM_ROOT%\integrations\richeclipse3.x`

**NOTE** In Visual Studio 2010 (and later) the Eclipse integration is installed in the Visual Studio experimental instance. This may affect your ability to debug your own plugin development.

To download the installer, contact [Support](#).

### *Installing the Integration*

- 1 As a user with administrative privileges run the installer.
- 2 Read and accept the license agreement.
- 3 Accept the default Dimensions CM installation folder or select a different one.

- 4 Specify the location of Eclipse.
- 5 Click **Install**. When the installation is complete click **Done**.

### **Post-Installation Tasks**

If you are using Version 6.2 of ActivClient for Common Access Card SSO logins change the location of the smart card library.

- 1 In Eclipse go to:  
Window | Preferences | (Version Control) Team | Dimensions CM
- 2 Change the smart card library path to:  
`\Program Files\ActivIdentity\ActivClient\acpkcs211.dll`

**TIP** You may need to reboot the machine to make the smart card login option available in Eclipse.

## **Silently Installing the Integration**

You can silently install the Eclipse integration. A silent installation is an installation where no user interaction is required.

- 1 Log in as a user with administrative privileges.
- 2 Navigate to the CM installer Eclipse integration folder and copy this executable and its associated files:  
`setup-windows.exe`
- 3 Copy the files to the folder you are using for the Eclipse integration silent installer files.
- 4 In a command prompt, navigate to the silent installer folder and run this command:

```
setup-windows.exe -i silent
```

You can optionally specify a response file from which the installer retrieves the values for various variables used to control the installation. To record your responses, specify `-r fileName`. To use the response file, specify `-f fileName`.

**NOTE** The uninstaller is `uninstaller.jar` in the Dimensions CM for Eclipse installation folder.

---

# Installing Other Integrations

Other Dimensions CM for Windows integrations are available. For details, contact [Support](#).

See the following Dimensions CM guides for configuration and connection information:

- *Dimensions CM Connect for SBM Guide*
- *IDE User's Guide*
  - Doors
  - ALM Quality Center
- *Dimensions Build online help*
  - Maven





## Chapter 6

---

# Post-Installation Tasks

Server Post-Installation Tasks	98
Agent Post-Installation Tasks	113
Client Post-Installation Tasks	114

**NOTE** To perform post-installation tasks, log in to CM as a user with administrator privileges.

# Server Post-Installation Tasks

## Checking a Server Installation

### *Installation Logs*

Check the installation logs before running any tests:

%DM\_ROOT%\InstallTemp

### *Server and Agent Acceptance Tests*

- 1 In Administrative Tools, open Services.
- 2 Check that the following services have the status Started and startup is set to Automatic.

- Dimensions CM:

OpenText Common Tomcat  
Dimensions Listener Service  
License Server

- Oracle Enterprise:

Oracle<oracle\_service\_name>TNSListener  
OracleService<oracle\_service>

- SQL Server:

SQL Service <instance\_name>

#### **NOTES:**

- If the Dimensions Listener Service fails to start automatically on reboot, start it manually once the RDBMS database service has started.
- The default Oracle<oracle\_service\_name>TNSListener is:  
OracleDimensionsTNSListener
- The default OracleService<oracle\_service> is:  
OracleServiceDIM14

- 3 Open the Windows task manager and check for the following processes:

- 
- Dimensions CM

`dimensions_service.exe`  
`dmappsrv.exe` (Oracle only)  
`dmappsrvn.exe` (SQL Server only)  
`dmemail.exe`  
`dmtnsr.exe`  
`dmpool.exe`

There are multiple instances of `dmappsrv.exe`.

- Oracle Enterprise:

`oracle.exe`  
`TNSLSNR.EXE`

- SQL Server:

`sqlserver.exe`

- 4 Open a command prompt, enter `dmcli`, and log in to CM. The output should be the Dimensions CM version number followed by a `Dimensions>` prompt.
- 5 Enter `exit` to return to the command prompt.

## Checking a Database Installation

- (Oracle only) Add the connection details to `tnsnames.ora`.
- (SQL Server only) Create an ODBC DSN connecting you to the database containing the schema. For details see [page 50](#).
- The file `%DM_ROOT%\dfs\listener.dat` contains the following default values:

```
-dsn cm_typical@dim14  
-initial 0
```

Edit the `-dsn` entry to be the `<database>@<dsn>` for the database containing the schema and restart the Dimensions Listener Service.

- Run the Dimensions CM `dmpasswd` utility against the schema you plan to use, for example:

```
dmpasswd cm_typical@dim14 -add -pwd cm_typical
```

For a Dimensions CM plus schema installation, this step is automatically performed by the installer, it only being required normally for additional base databases for such an installation.

For details about `dmpasswd`, see the *Administration Guide*.

- To start the server as `dmsys` rather than the user with local administrative rights who installed it, see [page 100](#).
- If you installed or configured an SSO server and configured a smart card, the login process is different, see the *online help*.

## Starting a Server in Restricted Mode

By default the CM service, Dimensions CM Listener, is owned by the user with local administrative rights who installed the product. You can change the owner to the CM system administrator.

- 1 In Administrative Tools open Services.
- 2 Shut down the Dimensions CM Listener Service service.
- 3 Log out as the user with local Windows administrative rights and log back in as the system administrator.
- 4 Navigate to:  
`%DM_ROOT%\dfs`
- 5 Add the following entries to the file `listener.dat`:  
`-user <DSA_username>`  
`-restricted_mode`  
where `<DSA_Username>` is the system administrator who runs the listener on the server (typically `dmsys`).
- 6 Restart the listener service.

**IMPORTANT!** When running a server in restricted mode, area/remote node authentication credentials are not used. In restricted mode files in a remote area are owned by the user running the `dmpool` process (by default `dmsys`), regardless of which user-id is set for the area or specified in remote node authentication.

---

## Licensing Dimensions CM

For details on managing licenses with the AutoPass License Server (APLS), see the [Dimensions CM online help](#).

**NOTE** Dimensions CM no longer supports licensing with SLM.

## Registering Base Databases

Every base database that connects to CM must be registered using the `dmpasswd` utility. Registration is automatic for the base database that you select during installation. The default password is `cm_typical` for the Qlarius demonstration product.

- To register other base databases:

```
dmpasswd <basedb>@<connect_string> -add -pwd <password>
```

- To change the password assigned to a base database:

```
dmpasswd <basedb>@<connect_string> -mod
```

You need to specify the old password and then the new one.

## Database Administration Acceptance Tests

- 1 Run the `dmdba spac` command (available for Oracle Enterprise only) and verify that the output is correct.
- 2 Run the `dmdba lsdbs` command and verify that the output is correct.
- 3 Run the Dimensions CM `UREG` and `XREG` commands to verify that you can create and drop users.

For information about the commands, see the *Administration Guide*.

## Command-Line Acceptance Tests

Run these tests from a valid Dimensions CM user account.

- 1 Open a command prompt, enter `dmcli`, and log in to CM.
- 2 Run the `LWS` command and verify that a list of projects is returned.

- 3 Run the SCWS command and verify that the correct project details are displayed.
- 4 Run the LWSD /RECURSIVE command and verify that a list of project directories and items is displayed.

## Multi-Homed Servers

**NOTE** The term "multi-homed server" should not be confused with Oracle-multiple-home installations.

Certain types of server platform (usually called "multi-homed") have more than one network adapter card and therefore more than one TCP/IP address.

Dimensions CM Make requires a TCP/IP address to enable communication between the Dimensions CM client and server processes. For Make to work on a client accessing a server on a multi-homed server, specify the appropriate TCP/IP address on the server by setting the MCX\_LISTEN symbol in the %DM\_ROOT\dm.cfg command file.

## Installing Dimensions Published Views

Published Views are automatically installed if you select the *Typical*, *Stream Development* or *Typical, Non-Stream Development* process models during installation.

To re-install and re-grant publish views to report users for each database:

- 1 Log in to dmdba as the Dimensions CM RDBMS administrator.
  - Oracle Enterprise: system
  - SQL Server: pcms\_sys
- 2 Enter the following commands:

```
delv <basedb>
insv <basedb>
grtv <basedb> <basedb_report_user_name>
```

For example:

```
grtv intermediate intermediate_rept
```

---

or

```
grtv cm_typical cm_typical_rept
```

This initial invocation of `grtv` sometimes results in an error stream starting with:

```
SQL-1E36-40(00B0FE60) ORA-  
00955: name is already used by an existing object
```

You can safely ignore these errors.

- 3 Enter the following command:

```
rekv <basedb> <basedb_report_user_name>
```

The following message should return:

```
Report views have been successfully revoked.
```

- 4 Enter the following command:

```
grtv <basedb> <basedb_report_user_name>
```

The following message should return:

```
Report views have been successfully granted.
```

- 5 Repeat this procedure for all report users in every base database on your server.

For more information about published views see the *Reports Guide*.

## Setting Configuration Variables

All Dimensions CM configuration variables are specified in the `dm.cfg` server file in the folder `%DM_ROOT%`. You do not need to modify this file unless you want to customize your environment. See the *Administration Guide* for details.

## Web Client Acceptance Tests

- 1 Log in to the web client:

Start | Dimensions <version> | Web Client

- 2 Click the **Items** tab and check that you can navigate around the project folder structure.
- 3 Check that you can browse items.
- 4 Check that the item history for items can be displayed.

## Administration Console Acceptance Tests

- 1 Log in to the Administration Console:  
Start | Dimensions <version> | Administration Console
- 2 Select a valid product and navigate to the **Object Type Definitions** section.
- 3 Verify that each of the lists of items and baselines are displayed and correct.
- 4 Select the **Lifecycles** section for a specified item type and verify that the details shown are correct and can be navigated.

## File System Considerations for Server Binaries

Server binaries should be installed on a Windows Server NTFS file system, for details see [page 179](#).

**NOTE** After installation of the binaries an administrator needs to secure server components and verify that all data files have the required access privileges, specifically they cannot be deleted by ordinary users. The administrator must be familiar with the workings of Dimensions CM and Windows server security policies. They must also guarantee that all changes to the access privileges are noted and tested to ensure that Dimensions CM continues to function correctly.



---

The following assets should be protected:

- Dimensions CM repository:
  - Database files
  - Product item libraries
- Executables and DLLs:  
All files in %DM\_ROOT%\prog
- Windows registry.

## SQL Server Enterprise Memory Usage

When you start SQL Server Enterprise memory usage may continue to increase even when activity on the server is low. This is normal behavior for the SQL Server buffer pool and does not indicate a memory leak. For details see the Knowledge Base Article 321363 in the [Microsoft help](#).

## Directories for Process Model Demo Products

Check that the following top-level deployment folders were created for the Qlarius demo product. If not create them manually:

```
C:\CM_Workarea\cm_typical\DEV
C:\CM_Workarea\cm_typical\LIVE
C:\CM_Workarea\cm_typical\PREPOD
C:\CM_Workarea\cm_typical\QA
C:\CM_Workarea\cm_typical\SIT
C:\CM_Workarea\cm_typical\WORK
```

## Configuring Trusted Certificate Authorities

For SSO and smart card installations, the most important part of authentication by certificate is checking that the certificate was issued by a trusted Certificate Authority (CA). To configure CAs correctly you should have your certificate authority (can be CA on a Microsoft Domain Controller or externally based on OpenSSL).

## ***Storing/Adding a Certificate in a Java Key Store***

The standard Java tool "keytool" can be used to perform various operations with Java Key Store (\*.JKS).

To create a new keystore or add a new certificate to existing keystore, use the following command:

```
"%JAVA_HOME%\bin\keytool" -import -keystore  
    <your_keystore_file_name> -storepass  
    <your_keystore_password> -file <cert_to_import> -alias  
    <your_cert_alias>
```

where:

<your_keystore_file_name>	Is the existing or new keystore file name to which the certificate is added.
<your_keystore_password>	Is the password for the keystore.
<cert_to_import>	Is the certificate to be added to the keystore. Can be *.PEM, *.CER (Base64 or DER encoded), or *.CRT.
<your_cert_alias>	Is the alias of the certificate in the keystore. Each certificate in the keystore has a unique alias/name.

## ***Configuring Truststore in the Security Server Identity Provider***

Specify one or more keystore and certificate aliases from the keystores in the X509-LDAP (or X509-BASE) authenticators of the IDP. Edit the main IDP configuration file located at:

```
<TOMCAT_HOME>\webapps\idp\WEB-INF\conf\Configuration.xml
```

The following sample and template shows how to configure trusted CAs, pay special attention to the CertificateIssuerTrustMatcher section.

---

```

<Setting Name="serena-ldap-authenticator" Type="htf:map">
  <Setting Name="Provider" Type="xsd:string">X509-LDAP</Setting>
  <Setting Name="CertificateMustExistInLDAP" Type="xsd:boolean">>false
  </Setting>
  <Setting Name="CertificateAttributeName" Type="xsd:string"></Setting>
  <Setting Name="SearchFilter" Type="xsd:string">(objectclass=*)</Setting>
  <Setting Name="CompatibleRequestMatchers" Type="htf:namedlist">
    <Setting Name="CredentialsTypeMatcher" Type="xsd:string">X509
    </Setting>
    <Setting Name="AuthenticationTypeMatcher" Type="xsd:string">*
    </Setting>
    <Setting Name="CertificateIssuerDNMatcher" Type="xsd:string">*
    </Setting>
    <Setting Name="CertificateIssuerTrustMatcher" Type="htf:map">
      <!-- Sample Entry -->
      <Setting Name="serena-truststore" Type="htf:keystore">
        <Setting Name="Type" Type="xsd:string">JKS</Setting>
        <Setting Name="File" Type="htf:file">serenaca.jks</Setting>
        <Setting Name="Password" Type="xsd:string">changeit</Setting>
      </Setting>
      <Setting Name="serenaca" Type="htf:certificate">
        <Setting Name="KeyStoreName" Type="xsd:string">serena-truststore
      </Setting>
      <Setting Name="Alias" Type="xsd:string">serenaca</Setting>
    </Setting>
    <!-- Template Entry -->
    <Setting Name="[your_keystore_alias]" Type="htf:keystore">
      <Setting Name="Type" Type="xsd:string">JKS</Setting>
      <Setting Name="File" Type="htf:file">[your_keystore_file_name]
      </Setting>
      <Setting Name="Password" Type="xsd:string">[your_keystore_password]
    </Setting>
    </Setting>
    <Setting Name="[your_certificate_alias(2)]"
    Type="htf:certificate">
      <Setting Name="KeyStoreName"
      Type="xsd:string">[your_keystore_alias]
    </Setting>
    <Setting Name="Alias" Type="xsd:string">[your_certificate_alias]
    </Setting>
  </Setting>

```

---

```
</Setting>
</Setting>
<Setting Name="JNDI.Environment" Type="htf:map">
  <Setting Name="java.naming.factory.initial"
    Type="xsd:string">com.sun.jndi.ldap.LdapCtxFactory</Setting>
  <Setting Name="java.naming.provider.url" Type="xsd:string">
    ldap://serena.com:389</Setting>
  <Setting Name="java.naming.security.authentication"
    Type="xsd:string">simple</Setting>
  <Setting Name="java.naming.security.principal"
    Type="xsd:string">ldapuser</Setting>
  <Setting Name="java.naming.security.credentials"
    Type="xsd:string">changeit</Setting>
</Setting>
</Setting>
```

where:

[your_keystore_alias]	Is any unique keystore name/alias, for example: my_company_ca_store
[your_keystore_file_name]	Is the existing keystore filename, full path, or relative path to the folder where Configuration.xml is located.
[your_keystore_password]	Is the keystore password.
[your_certificate_alias]	Is the existing certificate alias from [your_keystore_file_name].
[your_certificate_alias(2)]	Is any unique certificate name/alias, for example: my_company_ca-01 Can be the same as [your_certificate_alias].

**IMPORTANT!** After upgrading, if you use custom certificates with passwords that are not the default you need to update the configuration file shown above. The pre-14.x file is saved in the Tomcat 8.5 folder as:

backup\_config.pre<current CM version number>

Default password: changeit

---

## Dual Authentication

Dimensions CM supports dual username/password and smart card authentication.

For all other smart card users, it is often company best practice or mandated policy to ensure that such users do not have optional access to username/password authentication. In such circumstances, the operating system administrator should either:

- (Recommended) Never assign such users username/password authentication in the first place, or
- Ensure that username/password authentication is removed from all normal smart card users who have such authentication. For example, users with usernames that existed before smart card authentication was introduced.

## Establishing a Certificate Revocation List

A Certificate Revocation List (CRL) is one of the common methods when using a public key infrastructure for maintaining user access to servers in a network. The other, newer method, which has superseded CRL in some cases, is Online Certificate Status Protocol (OCSP).

The CRL is a list of subscribers paired with digital certificate status. The list enumerates revoked certificates along with the reasons for revocation. The dates of certificate issue, and the entities that issued them, are also included. In addition, each list contains a proposed date for the next release. When a potential user attempts to access a server, the server allows or denies access based on the CRL entry for that particular user. As part of smart card authentication, you have the option of comparing user certificates against one or more CRLs.

The main limitation of a CRL is that updates must be frequently downloaded to keep the list current. OCSP overcomes this limitation by checking certificate status in real time.

## Adding Smart Card Authentication

To add smart card authentication support to a server after installing Dimensions CM with SSO:

- 1 Open this file in an XML or text editor:

```
<TOMCAT_HOME>\webapps\idp\WEB-INF\conf\  
fedsrv-core-config.xml
```

- 2 Locate the `AllowedPrincipalAuthenticationTypes` parameter and add `CLIENT_CERT` to it. This enables the Smart Card Login button. The parameter should look like this:

```
<parameter name="AllowedPrincipalAuthenticationTypes"  
Type="xsd:string">CLIENT_CERT</parameter>
```

- 3 Save the file.

- 4 Open this file:

```
<TOMCAT_HOME>\webapps\idp\  
WEB-INF\conf\Configuration.xml file
```

- 5 Uncomment the X.509 authenticators by removing the `<!--X509-NAME and X509-NAME-->` markup. For example, remove the following markup to uncomment the X509-BASE, X509-LDAP, or X509-CRL authenticator:

```
<!--X509-BASE ... X509-BASE-->  
<!--X509-LDAP ... X509-LDAP-->  
<!--X509-CRL ... X509-CRL-->
```

- 6 Configure the Certificate Authorities (CA) in the X509-BASE and X509-LDAP authenticators, see [page 105](#).

For the X509-LDAP authenticator the following parameters must be substituted:

```
$X509_LDAP_HOST  
$X509_LDAP_USER  
$X509_LDAP_PASSWORD
```

By default, the installer configures the X509-LDAP authenticator when the smart card option is selected.

- 
- 7 The X509-CRL authenticator can be used in addition to X509-BASE or X509-LDAP. Substitute the \$X509\_CRL\_PATH parameter. The specified folder must contain \*.CRL files.
  - 8 Save the Configuration.xml file.
  - 9 Restart the OpenText Common Tomcat Service.

This Configuration.xml file contains the following commented out example of an authenticator. To use it, remove the comments and substitute the variables appropriate to your set up:

```
<!-- ===== -->
<!-- CRL validator against file based Certificate Revocation List -->
<!-- ===== -->
<!--X509-CRL
    <!--Setting Name="serena-crl-validator" Type="htf:map">
    <!--Setting Name="Provider" Type="xsd:string">X509-CRL</Setting>
    <!--Setting Name="CompatibleRequestMatchers" Type="htf:namedlist">
        <!--Setting Name="CredentialsTypeMatcher"
Type="xsd:string">X509</Setting>
        <!--Setting Name="AuthenticationTypeMatcher"
Type="xsd:string">*</Setting>
        <!--Setting Name="CertificateIssuerDNMatcher"
Type="xsd:string">*</Setting>
        <!--Setting>
        <!--Setting Name="CRLDir" Type="xsd:string">$X509_CRL_PATH
    </Setting>
        <!--Setting Name="CacheFileName"
Type="xsd:string">crl_cache.xml</Setting>
        <!--Setting Name="RefreshPeriod" Type="xsd:string">1200
        <!--Setting>
    </Setting>
X509-CRL-->
```

## SBM Smart Card Configuration Symbols

If you are only installing the SSO component to work in conjunction with SSO and smart card located on a Solutions Business Manager (SBM) installation, add the following SSO entries manually to the server `dm.cfg` file and restart the listener.

**NOTE** If you configure smart card setup when you install an SSO server the configuration symbols are automatically added to the `dm.cfg` file and assigned values:

- `SSO_SERVER_CERTIFICATE`
- `SSO_SERVER_PRIVATE_KEY`
- `SSO_SERVER_PRIVATE_KEY_PASSWORD`

See the *Administration Guide* for details.

## Integrating with Dimensions RM

To use the integration between Dimensions CM and Dimensions RM edit the RM server `rmcm.xml` file to provide the CM server URL.

- 1 On the Dimensions RM web server machine go to:

`<RM-Install-Directory>\conf`

- 2 Open the following configuration file in a text editor:

`rmcm.xml`

This file has the following lines:

```
<project>
    <!-- CMServer url="http://localhost:8080" -->
    <CMServer url="" />
</project>
```

- 3 Update the Dimensions CM URL with the correct server information. If CM is installed on the same machine as the RM web server and was installed with the default port number 8080, the commented out URL on the preceding line is correct.



---

## Create User Accounts

Create Windows operating system user accounts for each user in the sample process model you installed.

## Specifying a Whitelist of CM Server Connections

You can control which CM servers users can connect to by specifying a whitelist of base database and DSN combinations. All other connections are rejected.

- 1 Open the server listener file: %DM\_ROOT%\dfs\listener.dat
- 2 Add the following parameter:

```
-dsn_whitelist <basedatabse@DSN  
connection>,<basedatabse@DSN connection>...
```

For example:

```
-dsn_whitelist cm_typical@dim14,intermediate@dim14
```

## Deployment Automation Tasks

If you previously installed CM and Deployment Automation (DA) together and then upgraded them using the CM 14.5.1 or later server installers, edit the CM configuration file (dm.cfg) and change the following line:

```
DM_SDA_URL %DM_WEB_URL%/serena_ra
```

to

```
DM_SDA_URL %DM_WEB_URL%/da
```

## Agent Post-Installation Tasks

### Agent Acceptance Tests

See ["Server and Agent Acceptance Tests" on page 98](#).

## Error Messages in Server Event Viewer

When you start an agent error messages may be reported in the Windows event viewer. On a Dimensions CM agent installation, the %DM\_ROOT%\dfs\listener.dat file is not required. If the file is present, add the following line before restarting the Dimensions Listener Service to identify it as an agent installation:

```
-agent
```

## Client Post-Installation Tasks

### Checking the PATH Environment Variable

Check that the "prog" sub folder has been added to the PATH environment variable. Enter the following in a command prompt:

```
set path
```

Check that the path includes this entry:

```
C:\Program Files\OpenText\Dimensions <version>\CM\prog
```

If the entry is missing, add it using the method described [page 177](#).

### Using Internet Explorer to Access the Web Client

If you are using Internet Explorer on Windows 7 or 8 to access the web client the security settings may prevent the client from reading or writing files to local disks. Recommended workaround:

- 1 In Internet Explorer open Internet Options.
- 2 Click the **Security** tab select the **Trusted sites** zone.
- 3 Check that **Enable Protected Mode** is not selected.
- 4 Click **Sites**.

- 
- 5 In the **Trusted sites** window add the Dimensions CM web server's address. If your web server is not configured for HTTPS you may need to unselect **Require server verification**.
  - 6 Restart Internet Explorer window.

## Setting Up Aliases to Access Remote Databases

Before any user on a client node can connect to a remote Dimensions CM database from the desktop client, a database connection string (Data Source Name) for the remote database must be defined on the remote machine. See the *Administration Guide* for details.

## Setting Up Access to Item Libraries on Remote Hosts

If your Dimensions CM item libraries are not on the same machine, set up the connection between the local node and the library node in the Administration Console. For details about the Administration Console functions, see the *Dimensions CM online help*.

## Importing Visual Studio Customizations

Installing the Microsoft Visual Studio integration deletes existing customizations. You can export your current customizations before installing the integration and then import them. For details, see [page 36](#).

## Setting Up the Dimensions SCC Interface

You can check the Dimensions SCC Integration component by running the SCC Diagnostics program:

- 1 Go to Start | Dimensions CM <version> | SCC Diagnostics
- 2 Click **Test** to initiate the diagnostic test.

If there are any problems with the installation of this Dimensions SCC Integration, see the *IDE Guide*.

**NOTE** An installation of the SCC Integration Windows client component must also be performed locally on the Windows Dimensions CM server node even if the integration component is not used on the server. This ensures that the Dimensions CM server message files are up to date. The message files contain error messages and SQL scripts used both by the server and client components.

## Setting Configuration Variables

See [page 103](#).

## PowerBuilder Issues on Windows Server

On a Windows server you may receive the following error message when connecting to Dimensions CM SCC Interface:

Unable to Read Registry Value:

Software\Serena\Dimensions\\PcmsScc\SCCServerName

**NOTE** The term 'server' refers to a specific sub-type of Windows platform. This should not be confused with a Dimensions CM server installed on any of the supported Windows platforms.

The registry value in HKEY\_LOCAL\_MACHINE is present and can be read through the registry editor. This is a generic problem for all PowerBuilder SCC interfaces. To access the Dimensions SCC Interface do one of the following:

- Check the users receiving this error are members of the Administrators Group.
- In `regedit` check the permissions on this registry key:

```
HKEY_LOCAL_MACHINE | SOFTWARE | Serena | Dimensions |  
    <version> | PcmsScc
```

**Everyone** includes all of the following permissions:

Create Link	Write DAC
Write Owner	Read Control

Select the key and use the Security menu to modify the permissions.

## Chapter 7

---

# Pre-Upgrade Tasks

General Pre-Upgrade Tasks	118
Upgrading from Dimensions CM 2009 R2 and 12.x	120
Back up your Installation	122
SSO Server Tasks	123
Upgrading Deployment Areas	124
Upgrading the Eclipse Integration or Dimensions Make	124
Upgrading 2009 R2 Clients on Windows 64-Bit	125
Shut Down Dimensions CM	125
Closing the Microsoft Management Console	125
Verify the Database is Running	126
Download the Installer	126

## General Pre-Upgrade Tasks

- Check the [Support Matrix](#) for details about upgrades and supported versions.
- Back up non-OpenText applications inside the common Tomcat.
- If you are testing the upgrade process, we strongly recommend that you perform all tests with a copy of your current production base database on the same operating system.
- If you are upgrading server and client installations on the same machine, upgrade the server first.
- Verify that there is 3 GB of temporary space on the C:\ drive.
- The upgrade installer accesses information that was stored in the Windows registry when the software was installed. If your current installation has been moved, the upgrade may fail and you may have to reinstall the base software.
- (Oracle only) Check the consistency of the database sequence generator and fix any issues. See [Support knowledgebase solution S140907](#).
- Database administrator tasks:
  - Recalculate database statistics using the Dimensions CM DMDBA commands. For details, see [page 147](#).
  - (Pre-14 upgrade only) Increase the space allocated for the PCMS\_DATA and TEMP tablespaces by at least 50% and PCMS\_IDX by at least 100%.
  - (Recommended) Set the tablespaces PCMS\_DATA and PCMS\_IDX to AutoExtend.
  - Disable the Oracle recycle bin.
- If the variable DM\_DBCACHE\_DIR is set in dm.cfg, empty the specified location.

- 
- (Pre-14 upgrade only) Verify that all users have checked in or delivered their local modifications.

You can create a report in the desktop or web client to check which items are 'extracted' or 'locked' for all products in a base database. The administrator user can 'undo the checkout' of these items.

- Turn off all logging in `dm.cfg` and `listener.dat`.
- If you are going to upgrade your database manually from CM 12.x or earlier (install a server only and then run DMDBA), you must create the OpenText PulseUno user before upgrading.

**a** Stop Tomcat.

**b** Do one of the following:

- Oracle: Use SQLPlus create the user:

```
CREATE USER PULSE IDENTIFIED BY PULSE DEFAULT
TABLESPACE PCMS_DATA TEMPORARY TABLESPACE
PCMS_TEMP QUOTA UNLIMITED ON PCMS_DATA;
```

```
GRANT CONNECT, RESOURCE, CREATE VIEW TO PULSE
commit;
```

- SQL Server: Contact [Support](#) for details about how to create the user.

**c** Restart Common Tomcat.

# Upgrading from Dimensions CM 2009 R2 and 12.x

## To upgrade from Dimensions CM 2009 R2 and 12.x:

- 1 Run the latest 14.x Dimensions CM installer.
- 2 Run the Versioned Repository Schema (VRS) upgrade utility to upgrade the data in your RDBMS.
- 3 To prevent issues with data that was created with a pre-14.1.x release of Dimensions CM:
  - We recommend that users who have any pending changes deliver or check them in before you start the upgrade.
  - Run the UPDATE command after the upgrade to 14.x to also upgrade the metadata in your work areas.

The VRS upgrade retains all the existing project structure, project history, and baseline data. This avoids the need to upgrade all projects and baselines and ensures that an error during upgrade does not result in a loss of data. However, database size may increase dramatically as it contains both the old and new data. Before performing an upgrade you should increase the space allocated for PCMS\_DATA by at least 50% and the space allocated for PCMS\_IDX by at least 100%.

To prevent poor performance, recompute database statistics after an upgrade. If you choose to perform a series of partial upgrades, recompute statistics after each partial upgrade.

After all projects and baselines have been upgraded, you can drop the tables containing the pre-upgrade data. Back up and create an export of these tables (or the entire database) before dropping them:

```
XII_WS_FILES  
XII_WS_DIRS  
XII_PSH_REQ_RELS  
XII_PSH_PSH_RELS  
XII_PSH XII_PREV_CHANGES  
XII_PART_PART_RELS
```



---

XII\_PART\_ITEM\_RELS  
XII\_MIGRATED\_CHANGES  
XII\_ITEM\_SETS  
XII\_DP\_ITEMS\_SETS  
XII\_BASELINE\_ITEM\_FILES  
XII\_BASELINE\_ITEM\_DIRS

## Back up your Installation

**IMPORTANT!** Verify that both Dimensions CM and your RDBMS are shut down.

- 1 Back up your existing RDBMS database before you upgrade the schema. Use database tools to perform the backup (see the *Administration Guide*).
- 2 Back up item libraries using operating system tools.
- 3 Back up the current Dimensions installation using operating system tools or snapshots of virtual machines. At a minimum, back up the following files and directories:

**NOTE:** Back up the directories marked with an asterisk (\*) only if their files have been modified or customized.

```
%DM_ROOT%\dm.cfg
%$DM_ROOT%\dfs <directory>
*%DM_ROOT%\prog <directory>
*%DM_ROOT%\email_templates <directory>
*%DM_ROOT%\templates <directory>
%ProgramData%\OpenText\Dimensions CM\Bridge\conf
%ProgramData%\OpenText\Dimensions CM\Pulse\conf
%TOMCAT%\conf <directory>
%TOMCAT%\webapps\adminconsole\WEB-INF <directory>
%TOMCAT%\webapps\dimensions\WEB-INF <directory>
%TOMCAT%\webapps\bws\WEB-INF <directory>
%TOMCAT%\webapps\pulse\WEB-INF <directory>
%TOMCAT%\webapps\cmbridge\WEB-INF <directory>
```

- 4 If upgrading from CM 14.2.0.2 or later: Delete the contents of the Versioned Repository Schema (VRS) data cache directory:

```
%DM_ROOT%\db_cache_dir
```

---

# SSO Server Tasks

## SBM SSO Server Tasks

You can optionally use an SBM SSO server.

- To use an existing SBM Single Sign On (SSO) server, record the SBM server name and port number to connect to.
- Verify if a secure (HTTPS) connection is required.
- Export the STS certificate from the SBM SSO Server as a 'pem' file, *sts.pem*, so that it can be imported into Dimensions CM. For information see the *SBM Installation and Configuration Guide*.
- Determine how users are being validated and if Dimensions CM uses the same method. By default, internal SBM users for validation are used. The users need to be in both SBM and Dimensions CM with the same login ID. You can validate this with the SBM Configurator.

## Dimensions CM SSO Server Tasks

Dimensions CM can install its own SSO server for stand-alone applications.

- The following LDAP parameters are required:
  - Host name (by default, the same as for smart card reader)
  - SSO Port (by default, the same as for smart card reader)
  - Search filter
  - Bind user DN (by default, the same as for smart card reader)
  - LDAP password for the bind user DN (by default, the same as for smart card reader)
- If you are upgrading from a previous Dimensions CM SSO server, back up the following directories:

```
%TOMCAT%\alfssogatekeeper  
%TOMCAT%\..\jre\<version>\lib\security
```

In addition, for 14.3 or later:

```
%TOMCAT%/webapps/idp
```

- If you are using Secure Socket Layer (SSL) with SSO, you need the SSO server certificates and the trusted chain (including all root and intermediate certificates).

## Further Information

For more information about using SSO and SSL with CM, see the appendices in the *Administration Guide*.

## Upgrading Deployment Areas

Before you upgrade existing pre-Dimensions CM deployment areas to the current version (see [page 154](#)) perform a Dimensions CM AUDIT operation against the areas to check they contain the correct content.

## Upgrading the Eclipse Integration or Dimensions Make

To upgrade an existing Eclipse integration or Dimensions CM Make to the current versions do the following:

- 1 Uninstall the earlier version of the Eclipse integration or Dimensions CM Make. Make sure that the Eclipse IDE is shut down before uninstalling.
- 2 Delete the following folder:  
`%DM_ROOT%\integrations\richeclipse3.x`
- 3 Upgrade the Dimensions CM clients to the current release.
- 4 Install the current versions of the Eclipse integration or Dimensions CM Make.

---

# Upgrading 2009 R2 Clients on Windows 64-Bit

When you upgrade Dimensions CM 2009 R2 32-bit clients on Windows 64-bit platforms, a native 64-bit shell explorer is installed. To upgrade do the following:

- 1 Manually uninstall the Dimensions CM 2009 R2 32-bit client, see [page 173](#).
- 2 Install the native 32-bit Dimensions CM clients on the 64-bit platform, which also installs the 64-bit shell explorer, see [page 82](#).

## Shut Down Dimensions CM

- 1 Exit all Dimensions CM tools and applications and check that no users are accessing CM.
- 2 Shut down services for the Dimensions Listener and OpenText Common Tomcat.

### CAUTION!

- If Tomcat is running when you upgrade, the web archive ( .war ) files may not expand correctly.
- Check that the Services dialog box is closed. If it is open the Dimensions CM Listener Service may fail to start on completion of the installation.
- When you stop the Dimensions Service, the dmschedule and dmemail processes may continue to run for a period after the other processes have exited. Check that these processes have terminated before upgrading.

## Closing the Microsoft Management Console

Close the Microsoft Management Console before starting an upgrade.

## Verify the Database is Running

Check that the Dimensions CM database is active by connecting to it with standard database utilities.

Confirm that you know the database passwords for SYSTEM and PCMS\_SYS. You need to specify the passwords during a server upgrade installation for that RDBMS.

## Download the Installer

- 1 Download the installation files from [Support](#). There are separate files for server, agent, and client.
- 2 Unpack the files to a local folder.

## Chapter 8

---

# Upgrading Dimensions CM

Upgrade Options	128
Pre-Upgrade Tasks	128
Running the Installer	129
Upgrading all Server Components	130
Upgrading a Server Only	138
Upgrading Windows Agents	139
Upgrading Windows Clients	140
Verifying an Upgrade	141
Upgrading a Database	141
Silently Upgrading Agents	142
Silently Upgrading Clients	143
Post-Upgrade Tasks	143

# Upgrade Options

Upgrade Option	Components	See
Server and components	<ul style="list-style-type: none"><li>■ Server core files</li><li>■ Local or remote schema</li><li>■ OpenText Common Tools</li><li>■ Single Sign On (SSO) server</li><li>■ Smart card authentication</li><li>■ Deployment Automation (DA) server that enables you to publish and deploy artifacts</li><li>■ PulseUno and its modules, the Git and Vault servers</li></ul>	<a href="#">page 130</a>
Server only	Server only (no schema)	<a href="#">page 138</a>
Agent	<ul style="list-style-type: none"><li>■ Agent</li><li>■ Deployment Automation</li></ul>	<a href="#">page 139</a>
Client	Web client	<a href="#">page 140</a>
Database	Upgrade a database	<a href="#">page 141</a>

## Pre-Upgrade Tasks

Verify that you have completed the pre-upgrade tasks described in the previous chapter.



---

# Running the Installer

## Running the Installer from a DVD

- 1 Log in as a user with local administrative privileges and insert the DVD into the drive. If the HTML installation front end does not automatically start do one of the following:
  - Right click the DVD icon and select **AutoPlay**.
  - Run the appropriate file from the DVD drive.
- 2 Select **Click here >>**.
- 3 Select the component you want to install.

## Running the Installer from a Download

- 1 Open the folder containing the installer.
- 2 Log in as a user with local administrative privileges.
- 3 Run the appropriate installer:
  - Server: Dimensions\_CM\_Server\_<version>\_win64.exe
  - Agent: Dimensions\_CM\_Agents\_<version>.exe
  - Client: Dimensions\_CM\_Clients\_<version>.exe

### **IMPORTANT!**

Check that the folder common was extracted to the same location as the installers.

# Upgrading all Server Components

**IMPORTANT!** Your RDBMS must be running before you start the upgrade.

## SSO and Smart Card Limitations and Requirements

- The only smart card client reader supported is the Common Access Card (CAC), a United States Department of Defense (DoD) smart card issued as standard identification for logging in to DoD hosted software.
- Installing or configuring an SSO server requires specific Light Directory Access Protocol (LDAP) parameters. For details, see ["SSO and Smart Card Authentication" on page 28](#).
- Review the SSO and smart card prerequisites on ["SSO and Smart Card Authentication" on page 28](#).
- After upgrading Dimensions CM configured for SSO with a smart card, your SSO+CAC setup may not work due to the new string encryption mechanism in the updated software version. For details on how to re-enable the CAC authentication, see ["SSO and Smart Card Tasks" on page 152](#).

## Upgrading a Server with a PostgreSQL Database

- 1 Run the installer. See ["Running the Installer" on page 129](#). Read and accept the license agreement.
- 2 Select upgrade components:
  - **Dimensions Server**  
Upgrades the server and CM schema.
  - **Single Sign On**  
Installs or configures a connection to an SSO server.
  - **Smart Card Setup**

---

Configures smart card authentication.

- **Deployment Automation Server**

Installs a Deployment Automation server.

- **PulseUno**

Installs a PulseUno server (required) and its modules (optional):

- **Git server:** The server that PulseUno uses for Git repositories.
- **Vault server:** The server that PulseUno uses for the library of software packages.

**3** Accept the folder where Dimensions CM is installed or choose a different one.

**4** Select an SSO server installation option:

- **New:** Install a new SSO server.
- **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).

**5** Configure SSO and smart card:

- **Existing SSO server:** Specify the SSO server's host name and port. Optionally select a secure HTTPS connection.

- **New SSO server without smart card:**

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Defaults:

- Port: 389
- Search Filter:  
`(&(objectClass=user)(sAMAccountName={0}))`

- **New SSO server with smart card:**

- To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.

Default port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

`(&(objectClass=user)(sAMAccountName={0}))`.

After the upgrade is complete, manually configure the smart card trusted certificate authorities. For details, see ["Configuring Trusted Certificate Authorities" on page 105](#).

- 6** Select **Dimensions Server components and schema**.
- 7** Select the **PostgreSQL** database type.
- 8** Enter the name and password of the PostgreSQL SuperUser.
- 9** Enter the password for the PCMS\_SYS schema. Default: pcms\_sys
- 10** If prompted, enter the OS account name and password for the Dimensions CM system administrator. Default: dmsys
- 11** (Optional) Install a Deployment Automation server:
  - a** Select **Install DA**.
  - b** Accept the default installation folder or choose a different one.
  - c** (Optional if DA is already installed) Select **Use existing settings**.
  - d** (Optional) Select **Skip database creation**.
  - e** Specify the port number for Deployment Automation agents to make Java Message Service (JMS) connections to the server.
  - f** Select **Client Mutual Authentication** if you want Deployment Automation to use agent authentication when connecting to the server.
  - g** Specify a username and password for a new Deployment Automation database account to be created.

For details about installing and using DA, see [Support](#).

- 12** (Optional) Install the PulseUno modules:
  - **Install local Git server:** Installs the server that PulseUno uses for Git repositories.
  - **Install local Vault server:** Installs the server that PulseUno uses for the library of software packages.

---

The PulseUno server is installed automatically (required).

If you have the Git and Vault servers installed remotely, provide their connection details and optionally enable HTTPS.

- 13** Click **Install** to start the upgrade. When the upgrade is complete, click **Finish**.

## Upgrading a Server with an Oracle Database

- 1** Run the installer. See ["Running the Installer" on page 129](#). Read and accept the license agreement.
- 2** Select upgrade components:
  - **Dimensions Server**  
Upgrades the server and CM schema.
  - **Single Sign On**  
Installs or configures a connection to an SSO server.
  - **Smart Card Setup**  
Configures smart card authentication.
  - **Deployment Automation Server**  
Installs a Deployment Automation server.  
**IMPORTANT!** You must not install DA into a Serena-Supplied Runtime.
  - **PulseUno**  
Installs a PulseUno server (required) and its modules (optional):
    - **Git server:** The server that PulseUno uses for Git repositories.
    - **Vault server:** The server that PulseUno uses for the library of software packages.
- 3** Accept the folder where Dimensions CM is installed or choose a different one.
- 4** Select an SSO server installation option:
  - **New:** Install a new SSO server.

- **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).

**5** Configure SSO and smart card:

- **Existing SSO server:** Specify the SSO server's host name and port. Optionally select a secure HTTPS connection.
- **New SSO server without smart card:**

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Defaults:

- Port: 389
- Search Filter:  
`(&(objectClass=user)(sAMAccountName={0}))`

- **New SSO server with smart card:**

- To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.

Default port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

`(&(objectClass=user)(sAMAccountName={0})).`

After the upgrade is complete, manually configure the smart card trusted certificate authorities. For details, see ["Configuring Trusted Certificate Authorities" on page 105](#).

- 6** Select **Dimensions Server components and schema**.
- 7** Select the **Oracle** database type.
- 8** Select the Oracle installation.
- 9** Enter the user and password of the Oracle administration account.
- 10** Enter the password for the PCMS\_SYS schema for the Oracle instance.

- 
- 11** Enter the OS account name and password for the Dimensions CM system administrator. Default: dmsys
  - 12** (Optional) Install a Deployment Automation server:
    - a** Select **Install DA**.
    - b** Accept the default installation folder or choose a different one.
    - c** (Optional if DA is already installed) Select **Use existing settings**.
    - d** (Optional) Select **Skip database creation**.
    - e** Specify the port number for Deployment Automation agents to make Java Message Service (JMS) connections to the server.
    - f** Select **Client Mutual Authentication** if you want Deployment Automation to use agent authentication when connecting to the server.
    - g** Specify a username and password for a new Deployment Automation database account to be created.

For details about installing and using DA, see [Support](#).

- 13** (Optional) Install the PulseUno modules:
  - **Install local Git server:** Installs the server that PulseUno uses for Git repositories.
  - **Install local Vault server:** Installs the server that PulseUno uses for the library of software packages.

The PulseUno server is installed automatically (required).

If you have the Git and Vault servers installed remotely, provide their connection details and optionally enable HTTPS.

- 14** Click **Install** to start the upgrade. The installer:
  - Upgrades the Oracle tablespaces and sample process model. This may take a long time.
  - Upgrades the Common Tools (the Tomcat server, web client, and Administration Console).
  - Recalculates database statistics.

When the upgrade is complete, click **Finish**.

## Upgrading a Server with an SQL Database

- 1 Run the installer. See ["Running the Installer" on page 129](#). Read and accept the license agreement.
- 2 Select upgrade components:
  - **Dimensions Server**  
Installs the server and CM schema.
  - **Single Sign On**  
Installs, or configures a connection to, an SSO server.
  - **Smart Card Setup**  
Configures smart card authentication.
  - **Deployment Automation Server**  
Installs a DA server.
  - **PulseUno**  
Installs a PulseUno server (required) and its modules (optional):
    - **Git server:** The server that PulseUno uses for Git repositories.
    - **Vault server:** The server that PulseUno uses for the library of software packages.

For details about separating the database upgrade or migration operations from the server installation, contact [Support](#).
- 3 Accept the default installation folder or choose a different one.
- 4 Select an SSO server installation:
  - **New:** Install a new SSO server.
  - **Existing:** Configure a connection to an existing SSO server, for example, Solutions Business Manager (SBM).
- 5 Configure SSO and smart card:
  - **Existing SSO server:** Specify the SSO server's host name and port. Optionally select a secure HTTPS connection.
  - **New SSO server without smart card:**



---

To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Defaults:

- Port: 389
- Search Filter:  
(`&(objectClass=user)(sAMAccountName={0})`))

- **New SSO server with smart card:**

- To configure the LDAP connection for authenticating smart cards, enter parameters for Hostname, Port, Bind User DN, and Password.

Default port: 389

- To configure LDAP details for user credentials, enter parameters for Hostname, Port, Base DN, Search Filter, Bind User DN, and Password.

Search Filter default:

(`&(objectClass=user)(sAMAccountName={0})`)).

After the installation is complete, manually configure the smart card trusted certificate authorities. For details, see ["Configuring Trusted Certificate Authorities" on page 105](#).

- 6 For components, select **Dimensions server components and schema**.
- 7 Select the **SQL Server** database type.
- 8 Specify SQL Server Options:
  - a Select an existing SQL Server database you want to create an ODBC connection to.
  - b If the SQL Server is on a remote machine, select **Remote Database**.
  - c Accept the ODBC DSN or enter a different one.
- 9 Enter the password for the PCMS\_SYS schema for the CM schema.  
Default: pcms\_sys
- 10 If prompted, enter the OS account name and password for the Dimensions CM system administrator. Default: dmsys

- 11** (Optional) Install a Deployment Automation server:
  - a** Accept the default installation folder or choose a different one.
  - b** (Optional if DA is already installed) Select **Use existing settings**.
  - c** (Optional) Select **Skip database creation**.
  - d** Specify the port number for Deployment Automation agents to make Java Message Service (JMS) connections to the server.  
Default: 7918
  - e** Select **Client Mutual Authentication** if you want Deployment Automation to use agent authentication when connecting to the server.
  - f** Specify a username and password for a new Deployment Automation database account to be created.

For details about installing and using DA, see [Support](#).

- 12** (Optional) Install the PulseUno modules:
  - **Install local Git server:** Installs the server that PulseUno uses for Git repositories.
  - **Install local Vault server:** Installs the server that PulseUno uses for the library of software packages.

The PulseUno server is installed automatically (required).

If you have the Git and Vault servers installed remotely, provide their connection details and optionally enable HTTPS.

- 13** Click **Install**. When the upgrade is complete, click **Finish**.

## Upgrading a Server Only

- 1** Run the installer. See ["Running the Installer" on page 129](#). Read and accept the license agreement.
- 2** Select the **Dimensions Server** upgrade component.
- 3** Accept the folder where Dimensions CM is installed or choose a different one.
- 4** Select **Dimensions Server components only**.

- 
- 5 Click **Install**. When the upgrade is complete click **Finish**.

## Upgrading Windows Agents

- 1 Run the installer. See ["Running the Installer" on page 129](#). Read and accept the license agreement.
- 2 Read and accept the license agreements.
- 3 (Optional) Select the Deployment Automation agent feature.
- 4 Accept the default installation folder or select a different one.
- 5 Enter the host name and port number of the server that provides auto update install packages.
- 6 To configure the installation of a Deployment Automation agent:
  - Specify the name of a DA agent process.
  - (Optional) Select **Server Mutual Authentication** if you want the agent to use mutual authentication with SSL when connecting to the Deployment Automation server.
  - (Optional) Connect to an agent relay instead of directly to the Deployment Automation server. Specify the following parameters for the agent relay:
    - Host name or address. Default: localhost
    - Communication port. Default: 7916
    - HTTP proxy port: Default: 20080

If you are connecting directly to a Deployment Automation server, specify:

- The host name or address of the server.
- The Java Message Service (JMS) communication port.  
Default: 7918

For details about installing and using DA, see [Support](#).

- 7 Click **Install**. If you are prompted to reboot the machine click **OK**. When the upgrade is complete click **Finish**.

## Upgrading Windows Clients

- 1 Run the installer. See ["Running the Installer" on page 129](#). Read and accept the license agreement.
- 2 Accept the default installation folder or choose a different one.
- 3 From the Setup Type page, choose **Custom**.
- 4 On the Custom Setup page select the client features you want to install.

### NOTES

- If Microsoft Visual Studio is installed on the same machine, you can optionally install the Visual Studio integration.
  - Merge includes Araxis Merge, the default Dimensions CM merge tool, and the Merge Tool.
  - Windows Shell Explorer Extension enables you to launch the Dimensions CM Synchronize Wizard from Windows Explorer. For details, see the *Dimensions CM online help*.
  - Visual Studio Migration Tool does not require Visual Studio to be pre-installed. However, it does require Microsoft .NET Framework 3.5 or later.
- 5 (Optional) Specify the CM server connection details:
    - **Server Hostname:** The host name of a local or remote CM server.
    - **Database Name:** The database name on the server.
    - **Database Connection:** The database connection string.
    - **Port Number:** Accept the default port number for the Tomcat server (8080) or enter a different one if it is in use. Some software is hard coded to port 8080 and cannot be reassigned. See ["TCP/IP Port Usage" on page 25](#).
- NOTE:** You can also specify this information the first time you connect to a CM server.
- 6 Enter the host name and port number of the server that provides auto update install packages.

- 
- 7 Click **Install**. When the upgrade is complete, click **Finish**. Restart the machine when prompted.

## Verifying an Upgrade

See ["Server Post-Installation Tasks"](#) on page 98.

## Upgrading a Database

This section describes how to migrate to a later version of Oracle Enterprise. Some migration scenarios might require additional steps not documented below. See the [Support](#) knowledge base or contact the support team.

**IMPORTANT!** OpenText makes no warranty of any kind in regard to the contents of this chapter, including but not limited to implied warranties of merchantable quality or fitness for any particular purpose. OpenText shall not be liable for errors contained in it or for incidental or consequential damages in connection with the furnishing, performance, or use of this appendix or associated software. The information in this chapter is subject to change without notice.

### Typical Upgrade Scenario

- You have an existing CM production server running against a local Oracle Enterprise instance.
- The latest version of Oracle Enterprise demands more system resources and you have decided that you cannot upgrade the Oracle version on the existing server.
- You install Oracle Enterprise on a more powerful system.
- You migrate your existing production server and Oracle production databases to the new system and upgrade Dimensions CM.

## Upgrade Path

- 1 Stop the Dimensions CM listener.
- 2 On the new system create an Oracle instance. See ["Creating a Fresh Oracle Instance" on page 41](#).
- 3 On the new system install a Dimensions CM server with a local Oracle Enterprise. See ["Installing all Server Components" on page 62](#).
- 4 On the new system drop the pcms\_sys database and the demonstration database.
- 5 On the original Dimensions CM server export your existing Oracle pcms\_sys and demonstration databases.
- 6 On the new system import the database export file.
- 7 Manually upgrade the imported databases to use the new Dimensions CM schema:
  - a Log in to the dmdba utility as the Oracle Administration user (typically system):  

```
dmdba system/<system_password>@<connect_string>
```

For example:

```
dmdba system/manager@dim14
```
  - b At the SYSTEM> prompt enter the following dmdba command:  

```
upgrade all /force
```
  - c Exit dmdba.

## Silently Upgrading Agents

To silently upgrade an agent, see ["Silently Installing an Agent" on page 90](#). INSTALLDIR must specify the existing installation folder.

---

## Silently Upgrading Clients

To silently upgrade clients, see ["Silently Installing Clients" on page 85](#).

- Replace all command references of ADDLOCAL with REINSTALL.
- INSTALLDIR must specify the existing installation folder.
- If the existing clients were silently installed, use the full form of the command. Otherwise, some DLLs are lost during the upgrade.
- Use ADDLOCAL to add new clients.

## Post-Upgrade Tasks

See the post-upgrade tasks described in the following chapter.





## Chapter 9

---

# Post-Upgrade Tasks

Testing the Installation	146
Updating Tomcat Installations	147
Recalculating Database Statistics	147
Configuring a Deployment Server	147
Upgrading Pre-14.x Data	148
Server Post-Upgrade Activities	150
Visual Studio Customizations	154
Migrating Pre-Dimensions 12 Deployment Data	154

## Testing the Installation

- 1 Stop the Dimensions CM Listener and Tomcat services.
- 2 Verify that the database has been upgraded by running the following DMDBA command as your system user (Oracle) or pcms\_sys user (SQL Server):

```
upgrade all /force /logfile=<logfile.log>
```

Exit DMDBA.

- 3 If you previously made changes to the files listed below, merge the files that you backed up (see [page 122](#)) with the new versions that were installed during the upgrade:

```
%DM_ROOT%\cm\dfs\alf_events_config.xml
%TOMCAT%\conf\server.xml
%TOMCAT%\webapps\adminconsole\WEB-INF\web.xml
%TOMCAT%\webapps\dimensions\WEB-INF\web.xml
%TOMCAT%\webapps\bws\WEB-INF\web.xml
%TOMCAT%\webapps\pulse\WEB-INF\web.xml
%TOMCAT%\webapps\poolstats\WEB-INF\web.xml
%ProgramData%\OpenText\Dimensions CM\
    Pulse\conf\startup.properties
%ProgramData%\OpenText\Dimensions CM\
    Bridge\conf\startup.properties
```

- 4 Restart the Dimensions CM Listener and Tomcat services and verify that you can log in to the Administration Console.
- 5 Verify that you can log in to OpenText PulseUno:  

```
http(s)://<CM_Server>:8080/pulse
```
- 6 Check the [Support](#) website for any new patches for the version of Dimensions CM you are installing.

---

# Updating Tomcat Installations

Dimensions 14.6 and later uses Tomcat 9, which is located in the following directory:

`%DM_ROOT%\..\..\common\tomcat\9.0`

After a server upgrade, Tomcat webapps files for previous installations are located in one of the following directories:

- `%DM_ROOT%\..\..\common\tomcat\8.5`
- `%DM_ROOT%\..\..\common\tomcat\7.0`
- `%DM_ROOT%\..\..\common\tomcat\6.0`

For each application, determine if you can move it to the new Tomcat webapps folder or if a previous installation is required.

## Recalculating Database Statistics

We recommend that you recalculate database statistics regularly. Depending on the size of your database, this operation may take a few hours. When successfully completed, it speeds up queries and increases system performance.

To compute statistics, connect to the Dimensions CM database manager, DMDBA, as the system user and run this command:

```
dmdba system/sys_password@<dsn name>
connect base_db
statistics compute
```

For details about DMDBA, see the *Administration Guide*.

## Configuring a Deployment Server

If you are using Dimensions CM deployment, enable logging and configure the deployment server after upgrading. For details, see the [Dimensions CM online help](#).

## Upgrading Pre-14.x Data

If you are upgrading from a pre-Dimensions CM 14.x release you must upgrade your data to use the new Versioned Repository Schema (VRS). The upgrade is required to populate the VRS schema for the existing streams, projects, and baselines.

We recommend that you first upgrade recently used projects, streams, and baselines so that your users can start work immediately. Then upgrade the rest of the data. Dimensions CM operates normally while the upgrade utility runs in the background.

You can use the following methods to perform the VRS upgrade:

- The Versioned Repository Schema Upgrade GUI utility
- The dmdba command line

**IMPORTANT!** During the VRS upgrade the index tablespace(s) may increase by 50 percent. You may need to make the tablespace bigger before you start the upgrade.

### Using the VRS Upgrade Utility

- 1 Run the Versioned Repository Schema Upgrade utility:

From the Start menu, select **Dimensions CM <version> > Versioned Repository Schema Upgrade.**

- 2 In the login dialog box specify a schema name, schema password, and DB connection for the database you want to upgrade.
- 3 Click **OK**.

The Versioned Repository Schema Upgrade utility opens. It may take some time for the data to be loaded from the database. Navigate between the tabs to display the projects, streams, and baselines that can be upgraded.

- 
- 4 By default, all objects are selected initially. To modify the list of objects to be upgraded you can apply filters:
    - In the **Filter** box enter a value and from the list select one or more of these filters:
      - ID
      - Last Updated Date
      - Items
    - Select the **From and/or To** options and specify a date range.

**TIP:** Use the right-click menu to expand, collapse, check, and uncheck objects and trees.

**CAUTION:** By default all objects are selected. When you apply filters, all selected objects are upgraded, not just those displayed in the filter list. Deselect objects that you do not want to upgrade.
  - 5 To upgrade all the selected objects click **Upgrade**.
  - 6 Select the **Logging** tab to display details of the upgrade progress.
  - 7 When the upgrade is completed, click **Finish**.

## Using dmdba to Upgrade to VRS

Connect to the base database using the dmdba utility:

```
dmdba DB_name/db_password@db_connection
```

### To upgrade projects and streams:

Run the `upgradenvrs` command. You must use a pattern or list to specify the projects and streams to be upgraded:

- Project name or pattern: `PRODUCT:PROJECT,PRODUCT:%, %`
- List: specify a file containing a list projects and streams in `/B[ULK_FILE]=filename`

The file should have one stream or project per line followed by '/'.

**To upgrade baselines:**

Run the `upgradebln141` command. You can use a pattern or list to specify the baselines to be upgraded:

- Baseline name or pattern: `PRODUCT:BASELINE1, %`
- List: specify a file containing a list of baselines in `/B[ULK_FILE]=filename`

The file should have one baseline per line followed by '/'.

**To prepare streams for use in CM Bridge:**

If you are using CM Bridge run the `upgradecmbr` command to prepare your streams. You may use a pattern or list to specify the projects and streams to be upgraded:

- Project name or pattern: `PRODUCT:PROJECT,PRODUCT:%, %`
- List: specify a file containing a list projects and streams in `/B[ULK_FILE]=filename`

The file should have one stream or project per line followed by '/'.

## Computing Statistics

After completing the VRS upgrade, we recommend that you compute database statistics. See [page 147](#) for details.

# Server Post-Upgrade Activities

## Updating Database Views

**IMPORTANT!** The process described below is only required if the version of Dimensions CM you have upgraded to has additional base databases that were not included during the initial installation. The original base databases (for example, `qlarius_cm`) are automatically updated.

Do the following on each additional base databases:

- 1 Log in to `dmdba` as the Dimensions CM RDBMS administrator.

- 
- Oracle Enterprise: system
  - Microsoft SQL Server: pcms\_sys
- 2** Enter the following in a command prompt. <connect\_string> is the appropriate Database Source Name for the connection:

- Oracle Enterprise:

```
dmdba system/<system_password>@<connect_string>
```

For example:

```
dmdba system/manager@dim14
```

- For SQL Server

```
dmdba -ea dbo@<connect_string>
```

For example:

```
dmdba -ea dbo@dim14
```

- 3** At the SYSTEM> or PCMS\_SYS> prompt enter the following Dimensions dmdba command-pairs for each base database:

```
drop_base_views <BaseDatabase1> /Force
create_base_views <BaseDatabase1> /Force
drop_base_views <BaseDatabase2> /Force
create_base_views <BaseDatabase2> /Force
...
...
drop_base_views <BaseDatabaseN> /Force
create_base_views <BaseDatabaseN> /Force
exit
```

For example, for a Dimensions CM server that uses SQL Server and has the additional base databases test1 and test2 with the default <connect\_string> of dim14, enter.

```
C:\> dmdba -ea dbo@dim14
PCMS_SYS> drop_base_views test1 /Force
PCMS_SYS> create_base_views test1 /Force
PCMS_SYS> drop_base_views test2 /Force
PCMS_SYS> create_base_views test2 /Force
PCMS_SYS> exit
```

## Reinstalling Dimensions Published Views

After upgrading, reinstall all published views, see [page 102](#) and the *Reports Guide*.

## Rebuilding Developer Toolkit Applications

Rebuild existing API, web services, or custom integrations, for details see the *Developer's API Reference*.

## SSO SBM Server Tasks

- Replace the `sts.pem` file and update the file `$Tomcat\alfssogatekeeper\conf\truststore.jks`.
- If the SBM SSO Server is using SSL (https), the non-Java clients need to have the `$DM_ROOT\dfs\cacerts.pem` file updated so that it includes the JBOSS certificate and certificate chain in PEM format.
- Stop and restart the OpenText Common Tomcat and Dimensions CM listener.

## SSO and Smart Card Tasks

**NOTE** To implement smart card authentication after upgrading Dimensions CM with a Single Sign-On (SSO) server, see [page 110](#).

During an upgrade, if you installed an SSO server with smart card, see the following post-installation activities:

- ["Configuring Trusted Certificate Authorities" on page 105](#).
- ["Establishing a Certificate Revocation List" on page 109](#).

### ***Restoring SSO/CAC Customizations***

If your environment uses SSO with Common Access Card (CAC) enabled, the following folders are backed up during an upgrade:

- `tomcat\<version>\alfssogatekeeper`  
to  
`tomcat\<version>\alfssogatekeeper.pre.1.7.1.0`



- 
- tomcat\<version>\lib  
to  
tomcat\<version>\lib.pre.1.7.1.0
  - tomcat\<version>\webapps\idp  
to  
tomcat\<version>\webapps.pre.14.5.1\idp

If you customized your SSO configuration with new certificates, and made changes to the truststore and keystore, do the following:

- Manually restore your custom keystore files from the backup to the idp and alfssogatekeeper folders.
- Merge your custom changes into:
  - <TOMCAT\_HOME>\webapps\idp\WEB-INF\conf\ Configuration.xml
  - <TOMCAT\_HOME>\alfssogatekeeper\conf\ gatekeeper-core-config.xml

Do not replace these new .xml files with the backed-up versions.

After you upgrade Dimensions CM that uses SSO with a smart card, your SSO+CAC configuration may not work due to the new string encryption mechanism in the updated software version.

To enable the CAC authentication, re-encode all encoded values of type htf:encstring contained in this file:

```
<TOMCAT_HOME>\webapps\idp\WEB-INF\conf\  
Configuration.xml
```

To re-encode each value, run the sso\_encstring.bat command:

```
<TOMCAT_HOME>\bin\sso_encstring.bat" -e <value to  
encode>
```

For example:

```
C:\Program Files\OpenText\common\tomcat\9.0\  
bin\sso_encstring.bat" -e changeit
```

## Visual Studio Customizations

Updating the Visual Studio integration deletes existing customizations. For information about importing your customizations see [page 36](#).

## Migrating Pre-Dimensions 12 Deployment Data

You can migrate existing deployment data from pre-Dimensions CM version 12 to version 14 and use it with the new deployment model. There are two separate processes that enable you to use your existing deployment areas:

- The Dimensions CM 14 database upgrade that is performed automatically during installation.
- A manual standalone upgrade/migration process (documented [here](#)) that migrates your existing deployment information into the new Dimensions CM format first introduced in Dimensions CM 12.1. You can run this migration process when you are ready to bring a deployment area online for use in Dimensions CM 14.

### **IMPORTANT!**

- You cannot deploy to an area that has not been upgraded.
- You must upgrade the metadata in an area before upgrading it. For details about the *dmmeta* Metadata Utility, see the *Command-Line Reference*.

You can migrate existing deployment data from pre-Dimensions CM 12 to version 14 for one or all of your registered deployment areas. The areas being migrated must be online, accessible, and have valid login credentials specified against them for the migration process to work. For each area being migrated the process performs the following operations:

- Checks that the remote area is online and available.
- Scans the contents of the remote area for files that were placed there by Dimensions CM.
- Creates an initial area version that represents the current contents of that area based on the scan.

- 
- Creates an area audit trail that reflects the area version that was just created.
  - Validates that the area version just created is correct.

## Preparing for Migration

To successfully run the migration process, first decide which areas need to be migrated and have those areas online and available. By default, the migration process attempts to migrate all active deployment areas currently registered in your database. If you are using only some of your deployment areas, migrate only those and leave the others until needed.

Run the following checks against each area to ensure smooth migration (you should have previously run an AUDIT operation against each area before upgrading to Dimensions CM 14.5.1 or later; see [page 124](#), but that step is optional):

- Check the area is online and the accessible to Dimensions CM. If it is running on a Dimensions agent, verify that agent has been started and is running.
- Check the area definition has an area user and password associated with it. Failure to do so means that the migration of this area is skipped.

**NOTE** The following note applies only to areas hosted on z/OS mainframes on the MVS file system (not the z/OS UNIX file system).

The migration process described below explores all MVS data sets inside the area root. Some of the data sets may have been migrated to tape using the HSM product and the upgrade automatically recalls the data sets from tape. However, if this needs to be done for hundreds of data sets it can be a long process as they are recalled one at a time. We recommend that you perform the upgrade one area at a time (using the -area switch on the command) and make sure that all the relevant data sets are recalled prior to issuing the command. This is a more efficient than a bulk recall of all the data sets. You can also skip old areas that are no longer needed (these areas are likely to be on tape).

## Running the Migration Process

Run the migration process on a Dimensions CM 14.5.1 or later server installation using `dmdba`. See the *Administration Guide* for details about running `dmdba`.

For each Dimensions CM base database that you want to migrate:

- 1 Log in as a valid Dimensions CM administrator and setup the Dimensions environment.
- 2 Invoke DMDBA against either the SYSTEM (on Oracle) or PCMS\_SYS (MSSQL) databases:

```
dmdba system/manager@dim14 (Oracle)
```

```
dmdba -ea dbo@dim14 (MSSQL)
```

- 3 Run the following DMDBA command:

```
UPGRADEDEPLOY <baseDb>@<dsn>
```

where:

<baseDb>@<dsn> refers to the name of the Dimensions CM base database that you want to upgrade.

The UPGRADEDEPLOY command can also accept a number of optional qualifiers:

`-area <areaId>`

Forces the migration process to only process the specified area identifier. If this qualifier is not specified all registered deployment areas are migrated.

`-hidden`

Automatically registers any migrated files that are not displayed in the deployment views. For details on hidden objects, see the [Dimensions CM online help](#).

`-force`

Forces the migration process to attempt to re-migrate the area even if it has already been migrated.

Example commands:

- To upgrade all the deployment areas in CM\_TYPICAL:

---

```
SYSTEM> UPGRADEDEPLOY cm_typical@dim14
```

- To upgrade only the deployment area LIVE in CM\_TYPICAL:

```
SYSTEM> UPGRADEDEPLOY cm_typical@dim14 -area live
```

- To upgrade only the deployment area LIVE in CM\_TYPICAL and hide the migrated files:

```
SYSTEM> UPGRADEDEPLOY cm_typical@dim14 -area live -  
hidden
```

### ***Restrictions with the Migration Process***

- After you upgrade to Dimensions CM 14, the history for deployment areas only displays the new 'Deployment' event type and does not display pre-Dimensions CM 12 history. However, all of the pre-Dimensions CM 12 data can be queried from the PCMS\_PROMOTE\_HISTORY published view.
- The audit trail created by the migration process only consists of an initial area version and a list of all the items that are currently deployed to that area. Details of requests or baselines that might have also been deployed to that area are not created.
- When running the migration, any z/OS machines that are hosting deployment areas must have already been upgraded to the relevant Dimensions CM version. Otherwise, the migration fails.
- Items that have been upgraded as a result of this migration process cannot be rolled back unless they are specifically redeployed.

## **Upgrading and Maintaining the MO\_LIST Table**

The `build_upgrade_molist` utility program is used to:

- Convert Dimensions MO\_LIST rows so that the data items in this table reflect the latest definitions of the data items used in the product.
- Prune unnecessary records from the MO\_LIST structure.

You can run the utility repeatedly to perform pruning operations. However, it is most useful when converting to a version 14 database. Failure to run this conversion utility results in incorrect target determination during build processing and incorrect soft record processing.

[Support](#) can provide a process to help you check if the upgrade is required. Due to the existence of several paths to 14, some from earlier conversion processes, we recommend to run this process.

**TIP** The utility has a backup facility therefore you can use it with relatively low risk.

**NOTE** If you are not running Dimensions Build on MVS, you do not need to run this utility.

---

## **IMPORTANT!**

- You must run this utility before you perform any builds in Dimensions CM 14.
- The upgrade utility may delete rows from the MO\_LIST table. We recommend that you back up this table or the whole database before running the utility. As an added safeguard, the utility automatically makes a backup of the data.
- The utility can also be used, including after an upgrade, to reduce the size of the MO\_LIST table.

## **Overview**


The primary purpose of the utility is to manipulate the contents of the MO\_LIST table, which contains build relationships. While the utility is executing the database is not altered and is available. The utility outputs a text file containing the proposed rows. You can then inspect the file and load it into the target system using the -load command or an Oracle utility. There are multiple qualifiers to control the behavior of the commands.

The MO\_LIST table holds made-of relationships between items and items. It is used extensively in builds to determine what makes up an artifact. There are several sorts of records on this table. The records used by build have the flags 'O' and 'S':

- O: Hard or ordinary relationship records that record actual dependencies observed by the build system.
- S: Soft records that record putative relationships derived from hard relationships on an earlier version of a source item.

**NOTE** There are also M flag records placed on this table by dm\_make/mcxslave processing, but these are outside the scope of build.

The following diagram illustrates the data input and output flow:



### Unique Records

After the utility has completed an upgrade, each pair (`from_uid`, `to_uid`) is unique. This behavior optionally allows a new index to be created against the `MO_LIST` table, which may be useful in very large installations (see a [page 168](#)).

### Soft Relationships

A new set of soft records can be created by inspecting the existing relationships. The following should work as expected:

- Impacted target functionality.
- Build wizards.
- Newly edited versions of source files that have never been built.
- Older revisions which will never be built.



---

You can use this feature to create initial soft records when upgrading from an earlier version, or to replace the current set of records if they need to be reorganized.

### **Pruning Redundant Relationships**

If you have a very large number of rows on MO\_LIST the utility purges the redundant rows. This only has a small impact on functionality. The build wizards should work as expected on all source items revisions, even after a rollback, or when using an old baseline.

The following are retained:

- All item revisions of both sources and targets.
- Relationships from all source revisions, with a minimum of one revision of each target present at every stage of each lifecycle.

The only relationships that are removed are duplicate links, from a given source to multiple versions of the same target. However, older versions of targets (not sources) may not have made-of relationships recorded. If this is a problem then a purge can be optional. Purge can be mitigated by using the foot printing feature of Dimensions Build to record the makeup of each target. A source based impacted targets search works from any version of that source.

### **Syntax**

```
build_upgrade_molist
  [-f <parameter filename>]
  -direct dbname/dbpassword@conn | <server connection
    parameters>
  -process | -backup | -load | -report | -all
  <qualifiers>
```

where qualifiers can be:

Qualifier	-process	-backup	-load	-report	-all	Description
-trace	y	y	y	y	y	Turns on command tracing. <ul style="list-style-type: none"> <li>Options: 0, 1, 2</li> <li>Default: 0</li> </ul> Option 2 is only available in conjunction with the -spec qualifier to limit the scope of the operation.
-schema	y	y	y	y	y	Overrides a schema, for example: \ "ndp.\ " Applies to the MO_LIST table, WSFILES and WSDIRS.
-molist	y	y	y		y	Specifies a text file containing MO_LIST records.
-del			y			Deletes or replaces table rows. <ul style="list-style-type: none"> <li>Options: 0, 1, 2, 3, 9</li> <li>Default: 2</li> </ul>
-overwrite		y				Permits the overwrite of a backup file.
-product				y		Specifies a product.
-project				y		Specifies a project.
-filename				y		Specifies a mask to limit reporting.
-spec	y					Limits processing to specific item spec uids.
-drop	y					Drops relationships to target objects that match the specified mask.
-s	y					Creates soft records. <ul style="list-style-type: none"> <li>Options: 0, 1, 2</li> <li>Default: 1</li> </ul>
-o	y					Controls hard record pruning. <ul style="list-style-type: none"> <li>Options: 0, 1, 2, 9, 99</li> <li>Default: 9</li> </ul>

For full details of all the qualifier options see [page 165](#).

---

## ***Using a Parameter File***

Use the optional command `-f <parameter filename>` to read a file for additional parameters. This is particularly useful for options that are verbose such as `-drop` that can appear many times. It is easier to specify this list in a file, and refer to it with `-f`, than generate long commands.

Do not use parameters containing spaces inside the parameter file.  
Example:

```
-f parm.txt
```

## ***Logging into Dimensions CM***

- `-direct`

Use this option if you are local to the Dimensions Oracle instance to log in directly to the database without using Dimensions. Dimensions does not have to be running and users can use the tables when the utility is executing:

```
-direct \"dbname/dbpassword@conn\"
```

Example:

```
-direct intermediate/intermediate@dim14
```

- `<server connection parameters>`

Use this option to log in via a Dimensions server, which must be running.

```
-server          localhost:671
-user            dmsys
-password        dmsys
-database        intermediate
-conn            dim14
```

Example:

```
-server localhost:671 -user dmsys -password dmsys
      -database intermediate -conn dim14
```

## ***-process Command***

This command performs an upgrade of the build relationship data without altering the tables. It is a read-only process that creates a file containing

the changed data. You can then load the file into the database using the `-load` command or use Oracle techniques.

### ***-backup Command***

This command creates a text file of every row in the `MO_LIST` table.

**TIP** You could instead use Oracle's native backup features.

### ***-load Command***

This command loads a text file of build relationships into the `MO_LIST` table. This is the only command that writes to a table. This file can be a backup taken earlier with the `-backup` command or an upgraded table produced by the `-process` command.

**TIP** `sqlldr` in Oracle may be quicker for very large tables. For more information see [page 168](#).

### ***-report Command***

This command lists the relationships that are found against a set of source revisions. The filename does not include the path and is in Dimensions format. It is used in `LIKE " . . "` expressions in SQL therefore is case sensitive and can use `%` and `_` wildcards. For mainframe files, use `FOO.COBOL` rather than `COBOL(FOO)`.

Qualifiers:

- `-product` (case sensitive)
- `-project` (case sensitive)
- `-filename` (filename not the path)

Example:

```
-product PAYROLL  
-project TEST1  
-filename test.c
```

### ***-all Command***

This command executes a sequence of commands with pre-defined filenames. You can use it to run an upgrade with a single command. It is equivalent to the following sequence of commands:

---

```
-backup molist_backup.txt
-process molist_process.txt
-load molist_process.txt
```

### ***Qualifier Options***

Qualifier	Options
-trace	0: No tracing 1: Normal tracing 2: Use with the -report qualifier for more detail.
-schema	<p>The -process command requires these Oracle tables:</p> <ul style="list-style-type: none"><li>■ item_catalogue</li><li>■ ws_files</li><li>■ mo_list</li></ul> <p>Usually the tables all come from the schema you connected to with the -direct or -database options. However, you can get MO_LIST from a different schema if required, using the -schema qualifier. For this to work you need to grant access to MO_LIST to the user which you logged in with. This is useful if you have restored a backup into BACKUP.MO_LIST and need a matching ws_files and item_catalog in another database. You then run the following commands:</p> <pre>sqlplus backup/backup@dim14</pre> <p>For example:</p> <pre>Grant select, insert, delete on table backup.mo_list to intermediate;</pre> <p>You can load data into a foreign schema with the -schema qualifier. For example, this allows you to load the data into a test system. The table is called XXX.MO_LIST and the active user requires the GRANT INSERT permission.</p>

Qualifier	Options
-del	<p>-del &lt;sql delete option&gt; where option can be:</p> <ul style="list-style-type: none"><li>■ 0: No records deleted.</li><li>■ 1: Soft records deleted.</li><li>■ 2: Soft and hard records deleted.</li><li>■ 3: Hard records deleted.</li><li>■ 99: All records deleted.</li></ul> <p>The rows read from the file can either replace the rows already on the table or be merged with them. This depends on the -del qualifier that controls which rows on the current table are deleted. If you are merging records, the index constraints need to be obeyed. Typically, if you are creating a set of soft records, you delete all existing soft records with -del 1. If you are pruning redundant records, delete all records with -del 99.</p>
-spec	<p>-spec &lt;obj_spec_uid&gt;</p> <p>For testing and investigation, it is useful to limit the utility to process only certain items. You can do this by listing the OBJ_SPEC_UID values, for example:</p> <ul style="list-style-type: none"><li>-spec 8943226</li><li>-spec 9070313</li><li>-spec 9101070</li></ul> <p>List the source spec_uid and the target spec_uids if you want all the functionality to work as expected.</p>
-drop	<p>-drop &lt;sql like-clause&gt;</p> <p>Use this qualifier to drop relationships to certain types of target objects. Use it multiple times to get a list. The strings are used in LIKE "." SQL statements against WS_FILES.filename. For example:</p> <ul style="list-style-type: none"><li>-drop %.DBRM</li><li>-drop foo.obj</li></ul>

Qualifier	Options
-s	<p>-s option</p> <p>Creates soft records where option can be:</p> <ul style="list-style-type: none"> <li>■ 0: Do not create any soft records.</li> <li>■ (Default) 1: Create normal soft records.</li> <li>■ 2: Create fewer soft records than option 1 by un-duplicating records based on the textual filename. This is useful if you have many Dimensions objects with the same name.</li> </ul>
-o	<p>-o option</p> <p>Prunes hard records where option can be:</p> <ul style="list-style-type: none"> <li>■ 0: Do not create normal hard records.</li> <li>■ 1: Leave one relationship for each source/target/stage combination.</li> <li>■ 2: Leave two relationships for each source/target/stage combination.</li> <li>■ (Default) 9: Leave relationships that match the ws_files table criteria, for example, honor -drop.</li> <li>■ 99: Leave all relationships (-drop does not work in this case).</li> </ul> <p>Note: Even if you specify -o 99, records are still un-duplicated to create a unique (from_uid, to_uid) pair.</p>

### ***Reloading the MO\_LIST Table***

You can use the `-load` command to reload the table. However, for very large tables that exceed one million rows this might take a long time and put a strain on the Oracle re-do logs. It may be quicker to do the following:

- 1 Drop the MO\_LIST table and all its indexes.
- 2 Recreate the empty MO\_LIST table without indexes.
- 3 Use the sqlldr process from Oracle to reload data from the text file.
- 4 Recreate the indexes.
- 5 Grant again any accesses that are required.
- 6 Redo Oracle statistics.

You can perform step 2 by itself, but it is probably as fast as using the `-load` command.

An Oracle DBA can perform these steps by making note of how the table is currently set up so that it can be re-created in the same way (grants, indexes, and views). This process is quicker because the drop table is much faster than deleting all the rows (due to the re-do logs).

### **Using sqldr**

Create a text file called `molist-sqlldr.txt` similar to this:

```
load data
infile 'd:\molist_process.txt'
into table mo_list
fields terminated by "," optionally enclosed by '"'
( from_uid
, to_uid
, flag
, rule_uid
, build_uid
, from_fv
, to_fv
, from_workset_uid
, to_workset_uid
, from_virtual
, to_virtual
)
```

Note the `infile` syntax that names what the input file is. This is the file named by `-molist` in the upgrade command. For example:

```
sqlldr intermediate/intermediate@dim14 control=molist-
sqlldr.txt
```

### ***Creating New Indexes for the MO\_LIST Table***

This is an optional step and is only useful if you have a very large `MO_LIST` table with millions of rows. You can combine it with the `sqlldr` process or execute it after the table is up and running after using the `-load` command. After running the `-process` command with `-o 1,2` or `9`, the data is unique with respect to `(from_uid,to_uid)`. Certain operation in the server may be faster if unique indexes are created.

The following two indexes can be created:



---

```

CREATE unique INDEX nbp.mo_listu1 ON nbp.mo_list
(
    to_uid
    , from_uid
);

CREATE unique INDEX nbp.mo_listu2 ON nbp.mo_list
(
    from_uid
    , to_uid
)

```

Example of a full command:

```

CREATE unique INDEX nbp.mo_listu1 ON nbp.mo_list
(
    to_uid
    , from_uid
)
PARALLEL
(
    DEGREE 1
    INSTANCES 1
)
PCTFREE          10
INITTRANS        2
MAXTRANS         255
STORAGE
(
    INITIAL          65536
    NEXT             1048576
    MINEXTENTS       1
    MAXEXTENTS       unlimited
    FREELISTS        1
    FREELIST GROUPS  1
    BUFFER_POOL      DEFAULT
)
LOGGING
TABLESPACE        pcms_data
;

CREATE unique INDEX nbp.mo_list2 ON nbp.mo_list
(
    from_uid

```

```
                                , to_uid
)
PARALLEL
(
                                DEGREE          1
                                INSTANCES        1
)
PCTFREE          10
INITTRANS        2
MAXTRANS         255
STORAGE
(
                                INITIAL          65536
                                NEXT             1048576
                                MINEXTENTS        1
                                MAXEXTENTS        unlimited
                                FREELISTS          1
                                FREELIST GROUPS    1
                                BUFFER_POOL        DEFAULT
)
LOGGING
TABLESPACE        pcms_data
;
```

### ***Upgrade Example***

This example shows how to upgrade MO\_LIST using the build\_MO\_LIST\_upgrade utility.

#### **1** Back up the MO\_LIST table:

```
build_upgrade_molist \
    -direct intermediate/intermediate@d1222t0 \
    -backup \
    -molist ./backup-molist.out
```

This command:

- Copies all the data from the MO\_LIST table to a backup file.
- Does not make changes to the MO\_LIST table.
- Fails if backup-molist.out already exists. Use the qualifier -overwrite to overwrite it.

---

**2** Reads the MO\_LIST structure and obtains a report:

```
build_upgrade_molist \  
-direct intermediate/intermediate@d1222t0 \  
-report \  
-product ACCTS \  
-workset ACCTS \  
-filename %
```

This command:

- Reports on the MO\_LIST table contents.
- Does not change the MO\_LIST table.
- Sends the output file to stdout.

**NOTE:** -filename selects everything.

**3** Read and process the MO\_LIST structure:

```
build_upgrade_molist \  
-direct intermediate/intermediate@d1222t0 \  
-process \  
-molist ./trimmed-molist.out \  
-drop %.DBRM \  
-drop %.LNKLIB \  
-s 2 \  
-o 2
```

This command:

- Drops all relationships from source to DBRMs.
- Drops all relationships from LNKLIB outputs.
- Uses file names to reduce the number of soft records.
- Keeps two generations of source and target pairs.
- Writes the changed MO\_LIST data to trimmed-molist.out.
- Always overwrites trimmed-molist.out.
- Does not make changes to the database.



## Chapter 10

---

# Uninstalling Dimensions CM

Introduction	174
Uninstalling Components	174
Manually Uninstalling Windows Clients	176
Completing the Uninstallation Procedure	177

## Introduction

- Check that no Dimensions CM or RDBMS applications are running.
- If you are uninstalling a server and client installed on the same machine, uninstall the clients first.

## Uninstalling Components

### Stopping Services

Stop the following services:

- Dimensions CM:
  - OpenText Common Tomcat
  - Dimensions Listener Service
  - License Server
  - Dimensions CM HTTP/S Connector
- Oracle Enterprise:
  - Oracle<oracle\_service\_name>TNSListener
  - OracleService<oracle\_service\_name>
- SQL Server Enterprise:
  - SQL Service <instance\_name>
- PostgreSQL:
  - Dimensions\_Postgres\_Service

---

## Removing Programs

- 1 Depending on your version of Windows, open Add/Remove Programs or Programs and Features
- 2 Uninstall the following:
  - Dimensions CM Web Client Native Components*
  - Dimensions CM Web Client Tools*
  - OpenText Common Tools*
  - Dimensions CM Agents*
  - Dimensions CM Clients*
  - Dimensions CM for Eclipse <version>*
  - Dimensions Make <version>*
  - Dimensions CM Server*
  - AutoPass License Server*
- 3 When you are prompted to remove shared files, click Yes to All. It is not recommended that any Dimensions file be shared with other products.

## Undeleted Files

Some files in the CM home folder may not be deleted, for example:

- Activity logs
- Some configuration files
- Database files
- License files
- Files that were active or being accessed by an active process

You can safely delete these files.

## Undeleted Registry Keys

Some Dimensions CM installation-specific information is retained in the registry for reuse in subsequent installations. If you have removed all Dimensions CM products from your system you can remove this key and its contents:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Serena\Dimensions\<version>
```

## Uninstalling the Eclipse Integration

The Eclipse uninstaller requires Java. If you have Java version 7 or later, before uninstalling you must specify the path to LAX\_VM:

- 1 Open a command prompt and navigate to the location of the uninstaller.
- 2 Run this command: `setup-windows.exe LAX_VM "<path>"`  
where <path> must be the physical location of Java and not the linked directory that redirects to the physical location.

For example:

```
setup-windows.exe LAX_VM "c:\program files  
(x86)\Java\jre1.9.0_66\bin\java.exe"
```

## Manually Uninstalling Windows Clients

If the automatic uninstallation procedure fails you can manually uninstall the clients.

## Clearing Up Files

A failed automatic uninstallation procedure may not remove files. If these files do not contain data that you need to retain and you do not have a server installation on the same machine, complete the clearing up process by deleting the Dimensions CM folders %DM\_ROOT% or %PCMS\_ROOT%.



---

## Clearing Up Environment Variable

Update your PATH environment variable to remove the CM element. The default path is:

`C:\Program Files\OpenText\Dimensions <version>\cm\prog`

## Completing the Uninstallation Procedure

To complete the uninstallation procedure reboot the Windows machine. This is especially important if you are going to reinstall any of the Windows client components that you have just uninstalled.



## Chapter 11

---

# Item Library Security on NTFS Server

Protecting Item Libraries	180
Library Access Process	180
Item Library Node Location	181

## Protecting Item Libraries

Item libraries can be protected from unauthorized changes by setting an access control list (ACL) on each folder. ACLs are only allowed on NTFS file systems. We recommend that item libraries are not defined on FAT file systems.

To only allow a server to write files to item library directories, set the following ACL attributes:

- System: Full Control
- Administrators: Read Access
- Owner: Read Access

Do not give any users Write, Change, or Delete access.

## Library Access Process

The library access process Dimensions Listener Service is responsible for servicing PCMS\_SDP protocol connection requests. Messages generated by this service are placed in the Windows Server Event Application log.

If you locate item libraries on a disk that is mounted with non-standard access permissions you may need to change the login identity of Dimensions Listener Service. To change the identity:

- 1 Open Services.
- 2 Right-click Dimensions Listener Service and select **Properties**.
- 3 On the **Log On** tab select **This account** and entering the new identity.

---

## Item Library Node Location

Item libraries should be located on network nodes that can handle the load and are local to the users that most often access them.



## Chapter 12

---

# Troubleshooting

Troubleshooting Installation Issues	184
Troubleshooting a Windows Server	191
Miscellaneous	192

# Troubleshooting Installation Issues

## Installation Logs

To raise an installation ticket with [Support](#), zip up and attach the following logs:

- Dimensions server SDP trace.
- Tomcat startup.
- OpenText PulseUno and CM Bridge start up.
- OpenText Deployment Automation (DA) install.

For details about installing DA, see [Support](#).

## Dimensions Listener

Dimensions CM uses a listener process/service to manage access by clients to the server. If users are unable to connect to CM after an installation, this may be caused by the listener not starting successfully. Follow the procedures below to ensure that connection details are valid, and that the installation is properly configured.

- **Validate that the Dimensions Listener and pool management executables load and run successfully**

To validate that Dimensions CM has been installed correctly and that the executables can run without any issues, log in as the owner of the CM installation, set up the environment, and try to run the following executables from the command prompt:

```
dmlsnr  
dmpool  
dmappsrv
```

If any of these executables fail to run cleanly due to library or DLL loading errors, your installation may have failed to install properly. You need to determine why these loading errors are present before you can successfully run Dimensions CM. Common causes for such errors might be the failure to follow pre-installation requirements (for example, installing the necessary patches), running on a non-supported operating system, or that the environment is not set up



---

correctly. If none of these appear to be the case and re-installing Dimensions CM does not solve the issue, contact Serena Support.

- **Validate that the log in details used for the Dimensions CM pool are correct**

During the installation process you were prompted for details such as the user to own the Dimensions CM pool. If the details you supplied during installation are incorrect, the Dimensions Listener may fail to start. You can check if these login details are correct by utilizing a set of special initialization parameters that activate tracing of the Dimensions Listener and provide more details as to what the cause of failure might be. For instructions on how to activate this listener tracing, see [Enabling Dimensions Listener Tracing on page 192](#).

If the logs generated as a result of enabling the listener trace contain errors such as the ones below, it is possible that either the user name or associated password that you specified during the installation are wrong.

```
dmpool 2014/01/23 12:25:55 E P3036 T1204 password not
      set for user xxx\dmsys
dmpool 2014/01/23 12:25:55 E P3036 T1204
      StartUserProcess failed with 1326, Logon failure:
      unknown user name or bad password.
dmpool 2014/01/23 12:25:55 E P3036 T1204 xxx\xxx/
****, invalid user or password
dmpool 2014/01/23 12:25:55 E P3036 T1204 Cannot
      initialize pool
dmpool 2014/01/23 12:25:55 L P3036 T1204 Exiting
or
```

```
dmpool 2014/01/23 12:33:26 L P2208 T3648 DBS process
      created, id 928
dmpool 2014/01/23 12:33:26 L P2208 T3648 write message
      to process 928
dmpool 2014/01/23 12:33:26 L P2208 T3648 read message
      from process 928
dmpool 2014/01/23 12:33:26 E P2208 T3648 dmapprsv
      initialization failed, process 928
dmpool 2014/01/23 12:33:26 E P2208 T3648 Cannot
      initialize pool
dmpool 2014/01/23 12:33:26 L P2208 T3648 Exiting
```

You can correct these details as follows:

The username is specified by the `-user` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent). If this value is incorrect, edit this file to change the specified user.

To reset the associated user password used by Dimensions CM, do the following as the administrator of the installation:

```
dmpasswd <username> -del  
dmpasswd <username> -add -pwd <newPasswd>
```

where:

- `<username>` is the operating system user.
- `<newPasswd>` is the current password for this user.

#### ■ **Validate the system environment and registry entries**

Validate the environment set up from which you are trying to run Dimensions CM. This action is more applicable after an upgrade but the checks are valid for a fresh installation. To check the environment setup:

- Verify that your `DM_ROOT` variable is pointing to the correct installation and that the executables in the path are the correct ones. You might have earlier versions of executables from previous installations that are being picked up first. Ensure that your path is only picking up one installation of Dimensions CM.
- Check that your Windows system environment does not have `DM_ROOT` (or `PCMS_ROOT`) specified. These should only be specified in the Windows registry. If you have `PCMSDB`, `DMDB` or `LOCAL` set in your system environment, verify that they are pointing to the correct values. Do not specify these variables in the system environment unless absolutely necessary.
- Open your Windows registry hive and navigate to the following key:

```
HKEY_LOCAL_MACHINE/SOFTWARE/Serena/Dimensions
```

Under this key you can find entries for each of the versions of Dimensions CM that you have installed on your machine. For the version of Dimensions CM you are trying to run, navigate to that sub-key and verify that the following entries are present and point to the correct locations:

---

```
DM_ROOT
DimensionsStart
DimensionsStop
```

- **Validate that the socket you are using for the listener has not already been allocated or used**

It is possible that the socket service you have chosen for the listener to run on, as specified by the `-service` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent), is already being used. To validate the socket service:

- a Check that the `-service` parameter refers to a valid TCP/IP service name.
- b *Windows only:* Check that the socket service number has been specified in the `%DM_ROOT%/dm.cfg` file. The format for this specification is:

```
DM_SERVICE_<SERVICE_NAME>_TCP    <serviceNo>
```

where:

- `<SERVICE_NAME>` is the name of the TCP/IP service.
- `<serviceNo>` is the number associated with the socket.
- c Run the command `netstat -a` and check the output to determine if the socket you have allocated to Dimensions CM is already being used by another application. If yes repeat the steps above to reset the TCP/IP service number and try again.
- d If you are using firewalls or other network software/hardware, check that these have been correctly configured to allow communication on your chosen socket/service.

- **Validate that the Windows user has the correct privileges to run Dimensions CM**

Verify that the Windows user running `dmpool.exe` (by default SYSTEM) has the following Windows operating system privileges to enable them to run the executable:

- Act as part of the operating system
- Adjust memory quotas for a process
- Bypass traverse checking

- Create a token object
- Log in as a service
- Replace a process level token
- **Validate that the License Server is running**

If the listener is running properly, the next step is to validate that the License Server is running, or that the Dimensions CM server is configured to point to a valid license server.
- **Check the user's password**

For the user name that is specified by the `-user` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent), check that the operating system password for that user contains no underscore ("`_`") characters. If it does, reset the password using the appropriate operating system commands and through the `dmpasswd` utility as documented above.
- **Validate the ODBC DSN used for connections**

If you are using ODBC as the Dimensions CM database connection layer, validate that the name of the user specified by the `-user` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent) is not the same as your DSN name. Failure to do so may cause ODBC connection errors to occur.
- **Check SQL Net authentication errors using Oracle on Windows**

Under certain circumstances you may find that SQL Net (Oracle) fails to authenticate with your pool user. This issue has been seen on various Windows platforms when using Active Directory for user authentication. You can identify this issue by enabling listener tracing, see [page 192](#). Check the resulting trace logs in the `dmappsrv<processId>.log` files to see if you have Oracle connection errors. If you have errors, try changing the SQL Net authentication service:

Edit the contents of the file `sqlnet.ora` in your `%ORACLE_HOME%\NETWORK\ADMIN` folder.

If the file contains the line

```
SQLNET.AUTHENTICATION_SERVICES= (NTS)
```

---

change the line to read

```
SQLNET.AUTHENTICATION_SERVICES= (none)
```

and restart the listener.

- **Remove OPS\$ accounts when using Oracle and ODBC**

If the user managing the pool, as defined by the `-user` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent), has an OPS\$ account defined for them in Oracle, this can cause problems with ODBC connectivity.

To determine if this user has OPS\$ privilege, log in as that user and try the following command:

```
sqlplus /
```

If a connection to the database is established, run the following SQL commands to drop that OPS\$ account.

```
SQL> connect system/<system_passwd>  
SQL> drop user OPS$<userId> cascade;
```

- **Database connection errors**

If none of the suggestions above have helped, the next step is to verify the connection to the database by enabling listener tracing, see [page 192](#). After attempting to start the listener, look at the output from the log files that are generated. If these log files contain errors similar to the ones shown below, the database details specified by the `-dsn` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent) are probably incorrect. In the case of the Oracle below, the password details for the database have not been correctly registered:

```
dmappsrv 2014/01/23 12:33:26 E P928 T2516 Pcms error:
    1, Error: Unable to connect to database
    "cm_typical"
dmappsrv 2014/01/23 12:36:30 E P3864 T3572 Pcms error:
    1, Error: Schema version check failed for
    Dimensions database "cm_typical"
```

To verify that the database connection details are correct, use the RDBMS utilities such as TNSPING (Oracle) to validate that the DSN you specified exists, and that you can connect to it. Also, test the connection to the database specified through the `-dsn` parameter in the `%DM_ROOT%\dfs\listener.dat` file (Windows server or agent) or `$DM_ROOT/dfs/listener.dat` file (UNIX agent) file, and validate that the connection works.

If you are running against Oracle, use the Dimensions CM `dmdba cpas` utility to ensure that the database password for the database you are trying to connect to has been registered against Dimensions CM. Use `help cpas` within `dmdba` to ascertain the appropriate options.

If none of the above solutions help, contact Support for more assistance.

---

# Troubleshooting a Windows Server

This section addresses problems that have been reported by various customers while performing a Dimensions CM server installation on a Windows platform.

## Installation Problems

Problem	Cause and Solution
Dimensions Installer starts, but then exits.	<ul style="list-style-type: none"><li>■ Check your Windows log in user-id privileges. You must have administrator privileges to you start the Dimensions installer.</li><li>■ You are using a version of Windows that does not support a Dimensions CM server installation.</li></ul>
Installation stops because there is not enough disk space on the installation partition.	<ul style="list-style-type: none"><li>■ If the installation exits due to lack of disk space, uninstall the Dimensions CM server components before continuing, see <a href="#">page 174</a>. Before restarting the installation, ensure that the partition has enough disk space.</li><li>■ Check also that there is at least 3GB free space on the Windows System disk.</li></ul>
The installation terminates with an error message (other than those described below).	<ul style="list-style-type: none"><li>■ Check that your Windows user-id has full control over the installation folder and all its sub-directories. Before continuing, you may need to uninstall the Dimensions CM server components, see <a href="#">page 174</a>.</li></ul>
Other problems causing the installation to fail.	Uninstall the Dimensions CM server components and re-start the installation, see <a href="#">page 174</a> .

## Connection Problems

Problem	Cause and Solution
Unable to connect using the Dimensions desktop client.	<ul style="list-style-type: none"> <li>■ Check that all Windows service components have started on the server: <ul style="list-style-type: none"> <li>• All databases: <pre>Dimensions CM Listener Service License Server</pre> </li> <li>• Oracle: <pre>Oracle&lt;oracle_home_name&gt;TNSListener OracleService&lt;service_name&gt;</pre> </li> <li>• SQL Server: <pre>SQL Server &lt;instance_name&gt;</pre> </li> </ul> Restart services that are not started and try reconnecting to the client. </li> <li>■ You are not using a valid login in the Dimensions desktop client connection dialog.</li> </ul>
'... cannot find program ...' '... unable to load....'	Ensure that %DM_ROOT%\prog is included in your PATH environment variable.
License key not found.	<ul style="list-style-type: none"> <li>■ Check that you entered the license information correctly.</li> <li>■ On the server, enter the License Key as described in <a href="#">Chapter 5, "Installing Dimensions CM"</a>.</li> </ul>

## Miscellaneous

### Enabling Dimensions Listener Tracing

You may need to diagnose issues with the listener. Dimensions CM provides two special initialization parameters that you can use to start the listener in a mode that traces internal progress and status information to a log file for debugging purposes.



---

To enable tracing, uncomment and edit the following lines in the `listener.dat` file contained in the `%DM_ROOT%\dfs` folder (Windows server or agent) or `$DM_ROOT/dfs` directory (UNIX agent):

```
-tracedir <directory_name>  
-trace
```

where:

`<directory_name>` is the path where the trace files are to be created, for example: `c:\temp\tracedir`

After you have made this change, stop and restart Dimensions CM. To disable this tracing, comment out the two variables and restart Dimensions CM.

## Extracting Windows-Based Directory Items on Solaris

To store a Dimensions CM folder item on a Windows platform and extract it onto a Solaris platform with a directory pathname greater than 100 characters, install the publicly available GNU tar utility on both platforms. The utility is located in:

- (Windows) `%DM_ROOT%\prog`
- (Solaris) `$DM_ROOT/prog`

If you do not, the following error is displayed:

```
Error: unable to extract from archive file
```

This is caused by 100-character limitation being handled differently by the GNU tar utility and the native version of tar shipped with Solaris.

