

opentext™

LoadRunner Professional

Software version: 2023-2023 R1

Installation Guide

[Go to Help Center online](https://admhelp.microfocus.com/lr/)

<https://admhelp.microfocus.com/lr/>



Document release date: July 2024

Send Us Feedback



Let us know how we can improve your experience with the Installation Guide.

Send your email to: docteam@microfocus.com

Legal Notices

© Copyright 2023 Open Text.

The only warranties for products and services of Open Text and its affiliates and licensors ("Open Text") are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Open Text shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Disclaimer

Certain versions of software accessible here may contain branding from Hewlett-Packard Company (now HP Inc.) and Hewlett Packard Enterprise Company. This software was acquired on September 1, 2017 by Micro Focus and is now offered by Open Text, a separately owned and operated company. Any reference to the HP and Hewlett Packard Enterprise/HPE marks is historical in nature, and the HP and Hewlett Packard Enterprise/HPE marks are the property of their respective owners.

Contents

- Welcome to LoadRunner Professional 5
 - LoadRunner Professional Help Center 5
 - LRP components 6
 - Download installation packages 7

- System requirements and prerequisites 8
 - System requirements 8
 - Using TLS (SSL) certificates with LRP 8
 - Before you install 9

- Installing LRP components on Windows 12
 - Installation workflow 12
 - Upgrade LRP 14
 - Install LRP components using the Setup wizard 14
 - Running the installation 14
 - Setup wizard information 16
 - Install LRP components silently 18
 - Installation command line options 21
 - Installing the full LoadRunner Professional package from the wrapper file 21
 - Installing a standalone application or an additional component from a PFTW file ... 24
 - Install a LoadRunner language pack 26
 - Configure user login settings 26

- Installing a load generator 28
 - Install a load generator on Windows 28
 - Deploy Dockerized load generators on Windows 29
 - Prerequisites 29
 - Run a Dockerized load generator using the predefined image 29
 - Run a Dockerized load generator using a custom image 30
 - Examples of customized content for Dockerfiles 31
 - After running the load generator containers 33
 - Tips and guidelines 33
 - Installation workflow on Linux 34
 - Install a load generator on Linux with the Setup wizard 35
 - Silent load generator installation on Linux 37
 - Deploy Dockerized load generators on Linux 38
 - Prerequisites 38
 - Run a Dockerized load generator using the predefined image 39
 - Run a Dockerized load generator using a custom image 41

- After running the load generator containers 43
- Tips and guidelines 43
- Configure the Linux environment 44
 - Set the environment variables 45
 - Verify the Linux installation 46
 - Run verify_generator 47
 - Check Controller connection 48
- Improve load generator performance 49
 - Increase file descriptors 50
 - Increase process entries 51
 - Increase swap space 51
- Uninstall the load generator from a Linux machine 52
 - Uninstall load generator 12.55 or earlier 52
 - Uninstall load generator 12.56 or later 53
- Troubleshoot the load generator Linux installation 54

- Installing the LoadRunner Data Hub and Web Connector 60
 - Data Hub installation 60
 - Install the Data Hub with the Setup wizard 61
 - Install the Data Hub silently 61
 - Run a silent installation 62
 - Silent installation options 63
 - Verify the Data Hub installation 64
 - Web Connector installation 64
 - Install the Web Connector with the Setup wizard 65
 - Install the Web Connector silently 65
 - Run a silent installation 66
 - Silent installation options 67
 - Verify the Web Connector installation 68

Welcome to LoadRunner Professional

Welcome to the OpenText™ LoadRunner Professional Installation Guide.

LoadRunner Professional (LRP), a tool for performance testing, stresses your application to isolate and identify potential client, network, and server bottlenecks.

This guide describes how to install and set up LRP.

LoadRunner Professional Help Center

For context sensitive help within LRP components, press F1 within a dialog box or use the Help menu.

You can access the LoadRunner Professional and VuGen Help Centers on the web.

- <https://admhelp.microfocus.com/lr/>
- <https://admhelp.microfocus.com/vugen/>

When you open a link to a Help Center, make sure that the relevant product version is selected.

You can also download and install local versions of the help from the **Download Help Centers** page.

To switch between online and local modes, select **Help > Help Center Options > Open Online** or **Open Locally**.

Note:

- To view the Help Center in a browser or within VuGen, make sure JavaScript (Active scripting) is enabled in your browser settings.
- If the online Help Center is unavailable at the start of a LRP application session, the **Open Online** option might remain disabled during the whole session with that application.

LRP components

This installation guide describes the installation of the following LRP components. For more information about each of these components, refer to the [LoadRunner Professional Help Center](#).

Virtual User Generator (VuGen)	A tool for creating virtual user (Vuser) scripts, primarily through recording. Vuser scripts emulate users without a graphical user interface by using direct function calls.
Controller	Controls the execution of load and performance tests based on Vuser scripts. Includes the online monitors which monitor and display information about the test execution.
Analysis	Provides graphs and reports for analyzing the load test.
Load generator	Component for running Vusers (including Windows-based GUI Vusers) to generate load.
Network Virtualization	Enables you to generate the NV Insights Report, which provides an in-depth analysis of how your application performs over various types of networks. For details, see the Network Virtualization for LoadRunner Help .
Monitors over Firewall	Component on the agent machine for monitoring over a firewall.
MI Listener	Component for the MI Listener machine, used in running Vusers and monitoring over a firewall.
LoadRunner Data Hub	Communication channel that supports more robust communication between LoadRunner components.
Data Hub Web Connector	Enables the Data Hub to communicate via the web and over firewalls.

Standalone applications

Some of the components above are available for standalone installation. These can be found in the installation package's **Standalone Applications** folder.

Additional components

Additional components (such as the Citrix agent) can be found in the installation package's **Additional Components** folder. For details and installation instructions, see [Additional components and applications](#) in the LoadRunner Professional Help Center.

Download installation packages

You can access the installation packages from the [free trial](#) page or by selecting your account on the [Software Licenses and Downloads](#) page.

You can also download VuGen, LoadRunner Developer, VTS, LoadRunner Data Hub, and more, for free from [AppDelivery Marketplace](#).

System requirements and prerequisites

This chapter includes:

- [System requirements](#) 8
- [Using TLS \(SSL\) certificates with LRP](#) 8
- [Before you install](#) 9

System requirements

The following information can be found in the [Support Matrix](#):

- System requirements for running LRP components on a Windows system
- System requirements for running a load generator on a Windows or Linux system
- A full list of components that can be installed on the same physical machine at the same time

For system requirements and installation instructions for Network Virtualization, see the [Network Virtualization for LoadRunner Help](#). You can install Network Virtualization during the LRP installation, or at a later time.

Using TLS (SSL) certificates with LRP

During installation of some LRP components, you have the option to install CA and TLS (SSL) certificates.

These certificates are used for authentication and secure communication. Both certificates must be in *.cer (X.509) format.

- **CA certificate:** Enter the path to an existing certificate, or leave it blank to skip the step. The CA certificate should be generated in advance.
- **TLS certificate:** Select from an existing certificate file. Alternatively, the certificate can be generated automatically if you provide the CA certificate containing the private key.

For details on generating a CA certificate and working with certificates in LRP, see [Secure communication with TLS \(SSL\)](#) in the LoadRunner Professional Help Center.

Before you install

Before you install LRP components, review the information below.

For additional notes and limitations, see [Known issues](#) in the LoadRunner Professional Help Center.

Security review	We strongly recommend that you install LRP components on dedicated machines that do not contain, or provide access to, sensitive information; and that you do a thorough security review of the network topology and access levels in your testing environment.
Permission requirements	The installation process for all LRP components requires a full administrator account (root account for Linux systems) for all operating systems. You can install LRP components with UAC and DEP enabled, but we recommend to keep them disabled during installation (or enable DEP for essential Windows programs and services only). After installation, all of the LRP applications and components can run under a standard user account (an administrator account is not required), with UAC and DEP enabled.
Antivirus applications	It is recommended that you close all antivirus applications before installing LRP.

Running Web Services Vusers on Windows	<p>The Axis toolkit and WSE are no longer automatically installed with LRP. When running Web Services Vusers on a standalone load generator, some legacy configurations may require activation of .NET 3.5 (see MSDN), the inclusion of the Axis java files, or an installation of WSE (2.0 SP3 and WSE 3.0).</p> <p>To avoid using these components, recreate the scripts and import the WSDL using the default WCF toolkit.</p> <p>To use these components:</p> <ul style="list-style-type: none">• For WSE, install the WSE components from the OneLG installation package's folders, DVD\lranner\Common\wse20sp3 and DVD\lranner\Common\wse30, or download them from the Microsoft website.• For Axis, copy the Axis java files to %LG_PATH%\bin\java\Axis. For OneLG, the files are located in the prerequisites\Axis subfolder of the extracted installation package, by default <LoadRunner OneLG <version> root folder>\prerequisites\Axis. This allows you to run legacy scripts on an Axis toolkit. <p>For more details, see Known issues for Web Services.</p>
Running Java Vusers on Windows	<p>OpenJDK 32-bit is no longer automatically installed with LoadRunner. To work with Java protocols, you need to manually install a supported version of the JDK. VuGen uses internal logic to automatically detect your JRE version. For details, see Set up the environment for Java protocols.</p>
LRP and UFT coexistence	<p>If you install LRP and UFT on the same machine, and then uninstall one of them, the remaining software program may not function correctly.</p> <p>Resolution: Run a Repair of the software program you want to use on the machine.</p>

Licensing	<p>Note the following regarding LRP licensing:</p> <ul style="list-style-type: none">• To run Vusers with Controller, there must be a valid license installed on the Controller machine. LRP automatically installs the Community license bundle (free of charge) during LRP setup, providing 50 Vusers.• If upgrading from a version earlier than 2020, you need to replace your current license to work with the upgraded LRP installation. If you are using the Community license, it is automatically replaced during LRP installation. For any other license, contact licensing support to obtain a valid, compatible license. <p>For details on managing LRP licenses and extending your Vuser capacity, see About LoadRunner Professional licenses in the LoadRunner Professional Help Center.</p>
Custom certificates	<p>When upgrading from version 12.55 or earlier, if you used custom certificates in your previous installation of LoadRunner, install them again when prompted for certificates during setup. Otherwise, the setup program will overwrite them using the defaults.</p>
Network Virtualization	<p>If you choose to install NV automatically (as part of LRP installation), you must disable Windows SmartScreen before proceeding with the NV installation:</p> <p>Open HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Explorer in the Registry Editor, and change the Value data for SmartScreenEnabled to Off.</p> <p>Note: You do not need to disable SmartScreen when installing NV manually.</p>
Virtual environments	<p>The architectures provided by virtualization vendors are rapidly evolving. LRP is expected to function as designed in these changing environments, as long as the third-party vendor guarantees full compatibility of the virtualized environment with the LRP-approved hardware requirements. If you follow the system requirements and support matrix to create the virtual machine, LRP will work correctly.</p> <p>Working on top of a virtual machine may require access to the virtualization server hardware/monitoring environment, to ensure the virtualization server is not saturated; otherwise, this might obscure the virtual machine's measurements and lead to false results.</p>

Installing LRP components on Windows

This chapter describes how to install either the full version of LRP or an LRP component on a Windows platform.

This chapter includes:


- [Installation workflow](#) 12
- [Upgrade LRP](#) 14
- [Install LRP components using the Setup wizard](#) 14
- [Install LRP components silently](#) 18
- [Installation command line options](#) 21
- [Install a LoadRunner language pack](#) 26
- [Configure user login settings](#) 26

Installation workflow

The LoadRunner Professional installation package includes the Setup wizard that guides you through the process of installing the LRP components.

The final stage of the installation includes the optional installation of Network Virtualization.

Installing LRP on a Windows system involves the steps shown below:



1. Prerequisites

- Make sure that your system meets the hardware and software requirements. For details, see ["System requirements" on page 8](#).
- Review the information here: ["Before you install" on page 9](#).
- Installation must be performed at the destination machine. LRP does not support installation via terminal service.

2. Run the setup

- **Wizard installation:** To run the installation using the Setup wizard, see ["Install LRP components using the Setup wizard" on the next page](#).
- **Silent installation:** To perform a silent installation, see ["Install LRP components silently" on page 18](#).

After you run the setup, run any patch installations if necessary.

3. Install a language pack (optional)

After you complete the LRP installation, you can install a localized version to view the LRP, Analysis Standalone, and VuGen user interface in your local language. For details, see ["Install a LoadRunner language pack" on page 26](#).

4. Complete post-installation configuration

Configure LRP to run Vusers on a load generator machine without the need to log on manually. For details, see ["Configure user login settings" on page 26](#).

Upgrade LRP

LRP is a full installation that can be installed over any LoadRunner or LRP installation (version 12.5x and later).

To upgrade all components in your Windows installation using the Setup wizard, follow the installation process as described in ["Install LRP components using the Setup wizard" below](#). The installation process detects the older version and gives you the option to upgrade.

For silent upgrade, see ["Install LRP components silently" on page 18](#).

Install LRP components using the Setup wizard

This section describes how to install the full version of LRP, standalone components, or additional components using the Setup wizard.

Running the installation

The following procedure guides you through the Windows installation process.

To install LRP or an additional component:

1. Make sure the Windows Update process is not running on your machine.
2. Run the **setup.exe** file in the root folder of the installation package.

The LRP installation program begins and displays the installation options.

3. Select the required installation option. For details on each of the available components, see ["LRP components" on page 6](#).

For the machine that runs the load testing scenarios, select **LoadRunner Professional Full Setup**. The Full Setup includes the following components:

- VuGen
- Controller
- Analysis
- OneLG load generator
- Network Virtualization (optional)

Note: The LoadRunner Professional Setup wizard can install either LRP or LoadRunner Enterprise (LRE). Make sure to select **LoadRunner Professional**.

4. Specific software needs to be installed on Windows before you can install LRP (see the [Support Matrix](#)). If the prerequisite software is not already installed on your computer, a dialog box opens displaying the list of prerequisite programs that are required.

Click **OK** to install the listed software before continuing with the LRP installation. If you click **Cancel**, the LoadRunner Professional Setup wizard exits because LRP cannot be installed without the prerequisite software.

After installing prerequisite software, LRP may restart the machine. If that occurs, rerun **setup.exe**.

5. Perform the installation.

The Setup wizard opens, displaying the Welcome page. Follow the instructions in the wizard to complete the installation.

During installation of certain components, you have the option to install CA and TLS (SSL) certificates that will be used by the LoadRunner Agent. For details and requirements for these certificates, see "[Using TLS \(SSL\) certificates with LRP](#)" on page 8.

Note:

- The default installation path is: **C:\Program Files (x86)\Micro Focus\LoadRunner**

- The installation path cannot contain non-English characters.

6. After the installation is complete, you can choose to install Network Virtualization (NV).

In the Setup wizard, select:

- **Typical mode** for an automatic installation.
- **Custom mode** to change the installation folder, data folder, and the port.

For more details, see the installation section of the [Network Virtualization for LoadRunner Help](#).

7. If there is a patch available for the installed version:

- a. Run the patch installation file provided with the installation package.
- b. Follow the on-screen instructions.

Note:

- To repair the installation, run the **setup.exe** file located in the root directory of the LoadRunner Professional installation package, select **LoadRunner Professional Full Setup**, and then select the **Repair** option in the Setup wizard.
- For a list of the components that were registered during setup, such as **DLL** and **OCX** files, see the **RegisteredComponents_Micro Focus LoadRunner.txt** file in the **build_info** folder of the installation.

Setup wizard information

Review the following information to help you successfully install your LRP component using the Setup wizard. For more information on each component, refer to the [LoadRunner Professional Help Center](#).

LoadRunner Agent

Select the **Start LoadRunner Agent after installation** option to start the LoadRunner Agent on a load generator immediately after installation.

The agent enables communication between the load generator and Controller.

Agent mode	<p>During the installation of the OneLG load generator, MI Listener, or Monitors over Firewall components, you are prompted to select the mode for the installed LoadRunner Agent:</p> <ul style="list-style-type: none">• LoadRunner Professional mode. The agent runs as a regular process, requiring log in before the process can start. Select this mode if you are installing a load generator for use with Business Process Monitoring (BPM).• LoadRunner Enterprise mode. The agent runs as a service, and is launched automatically when the operating system starts.• LoadRunner Cloud mode. This is relevant for OneLG installation only. Select if you want to use the load generator with LoadRunner Cloud. <p>Agent configuration can be changed after installation, if required.</p>
Silk Performer Agent	<p>Select the Install Silk Performer Agent after installation option to install the Silk Performer Agent on a load generator that will be used to run Silk Performer scripts.</p>
Gatling	<ul style="list-style-type: none">• From version 2023 R1: Select the Install Gatling after installation option to install Gatling on a load generator that will be used to run Gatling scripts. This installs the Gatling version included with LoadRunner Professional.• Version 2023: The installation includes an embedded version of Gatling. No other installation or configuration is necessary. <p>Note: For manual installation, see Gatling tests.</p>
JMeter	<ul style="list-style-type: none">• From version 2023 R1: Select the Install JMeter after installation option to install JMeter on a load generator that will be used to run JMeter scripts. This installs the JMeter version included with LoadRunner Professional.• Version 2023: The installation includes an embedded version of JMeter. No other installation or configuration is necessary. <p>Note: For manual installation, see JMeter tests.</p>

Install LRP components silently

A silent installation is an installation that is performed without the need for user interaction. You use the command line to run the setup files. For details, see ["Installation command line options" on page 21](#).

Note:

- Use standard MSI command line options to define installation properties. For example, use `INSTALLDIR` to specify an alternate installation folder.
- To prevent the LoadRunner Agent on the load generator from starting immediately after installation, add the following to the command line command: `START_LGA=0`. The agent enables communication between the load generator and Controller. For more details on the LoadRunner Agent, see the [LoadRunner Professional Help Center](#).

To perform a silent installation of LRP:

1. Run one of the following commands from the command line:

- To install all of the LRP components including the prerequisite software in a single command:

```
<Installation_package>\lrunner\<>your_language_
folder>\setup.exe /s
```

- To first install all of the prerequisites, and then LRP, run the following commands:

```
<Installation_package>\lrunner\<>language_folder>\setup.exe
/InstallOnlyPrerequisite /s
```

```
msiexec.exe /qn /i "<Installation_
package>\lrunner\MSI\LoadRunner_x64.msi"
```

- By default, Network Virtualization is installed during the LRP installation. To facilitate this installation, add the following to the installation command:

```
REBOOT_IF_NEED=1
```

- To prevent the installation program from installing Network Virtualization, add the following to the installation command:

```
NVINSTALL=N
```

- To install Gatling or JMeter as part of the OneLG installation, add the following to the installation command:

Gatling:

```
INSTALL_GATLING=1
```

JMeter:

```
INSTALL_JMETER=1
```

Supported from version: 2023 R1. In version 2023, Gatling and JMeter are installed automatically.

- To secure your environment with TLS certificates and/or two-way TLS for LoadRunner products, OneLG, MiListener, or MoFW, add the following to the installation command as relevant:

```
CACERT = <path to the root certificate in *.cer format>  
CERT = <path to the server certificate in *.cer format>  
CACERT_PK = <the CA certificate private key>  
CACERT_PK_PWD = <password for the CA certificate encrypted  
private key>  
CERT_PK = <the TLS certificate private key>  
CERT_PK_PWD = <password for the TLS certificate encrypted  
private key>  
TWO_WAY_SSL = High | Medium
```



Example: The following command performs a silent installation of MI Listener.

```
SetupMILListener.exe /s /a /s INSTALLDIR="C:\Program Files (x86)\Micro Focus\MI Listener" IS_RUNAS_SERVICE=0 START_LGA=1 NVINSTALL=N CACERT=c:\temp\root.cer CERT=server.cer TWO_WAY_SSL=Medium
```

For certificate requirements, see ["Using TLS \(SSL\) certificates with LRP" on page 8](#).

- To install an LRP standalone application (not VuGen or OneLG):

```
<Installation_package>\Standalone Applications\Setup<component_name>.exe /s /a /s
```

- To install VuGen:

```
<Installation_package>\Standalone Applications\SetupVuGen.exe -s -sp"/s"
```

- To install additional components:

```
<Installation_package>\Additional Components\<setup_file_path> /s /a /s
```



Tip: See additional examples here: ["Examples " on page 25](#)

2. If you are installing an upgrade, run the following command:

```
msiexec.exe /update <full path to msp file> [/qn] [/l*vx <full path to log file>]
```

The msp files are located in the installation package.

For details, see ["Upgrade LRP" on page 14](#).

Installation command line options

You can use the Windows command line to install the full LoadRunner Professional package, standalone applications, and additional components. The CLI uses Wrapper file (setup.exe) or Package for the Web files (<PFTW>.exe).

- The full LRP installation can be launched using the setup.exe file. For details, see ["Installing the full LoadRunner Professional package from the wrapper file" below](#).
- The installations of standalone applications and additional components can be launched via PFTW files. For details, see ["Installing a standalone application or an additional component from a PFTW file" on page 24](#).

Installing the full LoadRunner Professional package from the wrapper file

You can install full LRP from the installation wrapper file, **setup.exe**, located in **\runner\ folder of your LoadRunner Professional installation package. The following command line options are available:**

Option	Description
/s	Runs the installation in the background (silently), with no user interaction.
/qb	Runs the installation in unattended mode, with limited user interaction.
/InstallOnlyPrerequisite	Installs only the prerequisites – does not install any LRP components. By default, the setup program checks that your machine has the required prerequisites, and installs them if necessary, before installing the LRP components.

You can set public properties for the command line installation, using the following syntax:

```
setup.exe PROPERTY_NAME="value"
```

The following properties are available:

Property name	Description
INSTALLDIR=" <i>your_path</i> "	Specifies the location where the application will be installed.
REBOOT_IF_NEED	1: Reboots the machine after installation, if required. This is recommended if you include the installation of NV (Network Virtualization). 0: Does not reboot the machine after installation. Default: 0
NVINSTALL	Empty string: Excludes the installation of the NV component. Y: Includes the installation of the NV component. Default: Y
INSTALL_NV_MODE	1: Sets the NV installation mode to Typical . 2: Sets the NV installation mode to Custom . Default: Typical
INSTALL_DIR=" <i>your_path</i> "	Specifies a path for the installation.
START_LGA	Empty string: Instructs the machine not to start the load generator after installation. 1: Instructs the machine to start the load generator after installation. Default: 1

Property name	Description
IS_RUNAS_SERVICE	<p>0: LoadRunner Professional mode, runs the load generator's agent as a process.</p> <p>1: LoadRunner Enterprise mode, runs the load generator's agent as a service.</p> <p>2: (Relevant for OneLG only) LoadRunner Cloud mode, runs the load generator's agent as a service, and triggers launch of LRC Agent configuration at the end of the installation.</p> <p>Default: 1</p>
INSTALL_SILK_PERFORMER_AGENT	<p>1: Installs the Silk Performer Agent on load generators (used to run Silk Performer scripts).</p>
INSTALL_GATLING	<p>Supported from version: 2023 R1. In version 2023, Gatling is installed automatically.</p> <p>0: Does not install Gatling on the load generator.</p> <p>1: Installs Gatling on the load generator.</p> <p>Default: 0</p>
INSTALL_JMETER	<p>Supported from version: 2023 R1. In version 2023, JMeter is installed automatically.</p> <p>0: Does not install JMeter on the load generator.</p> <p>1: Installs JMeter on the load generator.</p> <p>Default: 0</p>
SKIP_CHECK_PRIVILEGE	<p>0: The installation process checks the install path for access privileges.</p> <p>1: The installation process skips the access check for the install path.</p> <p>Default: 0</p>

Property name	Description
IMPROVEMENTPROGRAM	0: Disables the LoadRunner Improvement Program. 1: Enables the LoadRunner Improvement Program. Default: 1

Example:

The following command performs the installation silently and then reboots the machine if necessary:

```
DVD\lrunner\en\setup.exe /s REBOOT_IF_NEED="1"
```

Installing a standalone application or an additional component from a PFTW file

You can install an LRP standalone application or one of the additional components via the Package for the web (PFTW) files that are included with the LoadRunner Professional installation media. The installation files are located under the **Standalone Applications** or **Additional Components** folders on the installation media.

Double-click on the packaged file, or run it from the command line using the following options:

Option	Description
/s	Runs the installation in the background (silently), with no user interaction.
/e	Only extracts the installation files; does not run them.
/f	Specifies the path of a temporary folder for file extraction. For example: /f "c:\my_temp_folder" If you leave out this option, the default temporary folder is used.

Option	Description
/a	Allows you to pass parameters or properties to the autorun file, such as setup.exe. Use the properties defined above (in the wrapper file section) for the setup.exe file.

Note: Silent installation for VuGen and OneLG:

- **SetupVuGen.exe** and **SetupOneLG.exe** uses different install commands (see the examples below).
- If you need to insert a quotation mark character into the command line parameter, use two consecutive quotation marks.

Examples

The following commands silently run setup, and install the application in the specified folder. Where relevant, they also start the agent after installation:

- Examples for **SetupVuGen.exe** and **SetupOneLG.exe**:

```
SetupOneLG.exe -s -sp"/s INSTALLDIR=""C:\Program Files (x86)\Micro Focus\LoadRunner OneLG"" IS_RUNAS_SERVICE=0 START_LGA=1 NVINSTALL=N"
```

```
SetupVuGen.exe -s -sp"/s INSTALLDIR=C:\VuGen"
```

- Examples for **other standalone applications**:

```
SetupAnalysis.exe /s /a /s INSTALLDIR="C:\Analysis"
```

```
SetupMILlistener.exe /s /a /s INSTALLDIR="C:\MiListener"
```

```
SetupMoFW.exe /s /a /s INSTALLDIR="C:\MoFW"
```

Install a LoadRunner language pack

The language packs enable you to view the LRP user interface in your local language. You install the language pack for the relevant LRP component: LoadRunner Professional full, VuGen standalone, or Analysis standalone from the LoadRunner Professional installation package.

For a list of supported languages, see the [Support Matrix](#).

The language packs are supported for native non-English operating systems only.

Important: The native language of the operating system must be the same as the language pack you are installing. For example, the Spanish language pack must be installed on a machine with a native Spanish operating system.

To install a language pack:

1. Make sure that LRP in English is already installed.
2. In the root folder of the LoadRunner Professional installation package, run **setup.exe**. The LRP installation program begins and displays the installation options.
3. Click **Language Packs**. The Language Packs folder in the installation package opens.
4. Navigate to the folder for the language and component you want to install and run the installation file. For example, to install the French language pack on a VuGen standalone machine, the path is **..\Language Packs\French\VugenSA\Vugen_FRA.msp**.
Follow the online instructions.

Configure user login settings

By default, you need to manually log on to a computer before LRP can run Vusers on that computer. However, you can configure LRP to run Vusers on a load

generator machine, without the need to manually log on to the machine.

To configure user login settings:

1. In the Windows Start menu, search for **LoadRunner Agent** and select **LoadRunner Agent Runtime Settings Configuration**.

The LoadRunner Agent Runtime Settings dialog box opens.

2. Select one of the following options:

- **Allow virtual users to run on this machine without user login.** LRP automatically logs on to the network from the load generator machine, so the Vusers can run without any manual intervention. Enter the network domain where the user machine resides, a user name, and password.

Note: When created, the LoadRunner Agent service starts with the **LocalSystem** account (not as a specified user). The specified credentials are used by the agent service to start the **mdrv.exe** process when you run the script.

You must reboot and log on to the system at least once after the LRP installation before the automatic login can work.

- **Manual log in to this machine.** The user must manually log on to the network from the load generator machine for each session of running Vusers.
3. Click **OK**.

Installing a load generator

Load generators are the machines that run Vuser scripts to generate load. To create a load generator, you install the LoadRunner load generator software on a host computer. Load generators can be either Windows-based or Linux-based. You use the Windows-based LoadRunner Controller to control both the Windows-based and the Linux-based Vusers.

You can install a load generator using the UI-based setup wizard, perform a silent installation, or deploy a load generator using a Docker container. Alternatively, you can provision a load generator in a cloud account. For details, see [Load generators on the cloud](#) in the LoadRunner Professional Help Center.

This chapter includes:

- [Install a load generator on Windows](#)28
- [Deploy Dockerized load generators on Windows](#)29
- [Installation workflow on Linux](#)34
- [Install a load generator on Linux with the Setup wizard](#)35
- [Silent load generator installation on Linux](#)37
- [Deploy Dockerized load generators on Linux](#)38
- [Configure the Linux environment](#)44
- [Improve load generator performance](#)49
- [Uninstall the load generator from a Linux machine](#)52
- [Troubleshoot the load generator Linux installation](#)54

Install a load generator on Windows

To install a load generator on Windows, you use the same installation process as other LRP components. For details, see "[Installing LRP components on Windows](#)" on page 12.

To deploy a load generator on Windows using a Docker container, see "[Deploy Dockerized load generators on Windows](#)" on the next page.

Deploy Dockerized load generators on Windows

This section describes how to run a Dockerized load generator on a Windows platform. Docker is a platform that allows you to develop, ship, and run applications via a container.

For supported protocols on Dockerized load generators, see the [Supported Protocols](#) guide.

Note: FTP is not fully supported with load generator for Docker on Windows. Passive mode FTP is supported, but Active mode FTP is not.

Prerequisites

- Install Docker on the target machine, along with its dependencies, and set up the target machine environment as required. Currently, only the 64-bit version is supported. For installation details, see the Docker online documentation.
- Pull the Windows load generator Docker image from the from the relevant page, accessible from the performance testing page (<https://hub.docker.com/u/performancetesting>) in the Docker hub. Use the following command and appropriate **<tag version number>**, for example, 20.03:

```
docker pull performancetesting/microfocus_onelg_windows:<tag version number>
```

Note: The Docker image for the OneLG load generator replaces the previous Windows standalone load generator docker image.

Run a Dockerized load generator using the predefined image

Use the ready-to-use image to run a load generator (OneLG) on Docker for Windows. If you need customization for your container, for example, for Java or to

run under a specific user, see ["Run a Dockerized load generator using a custom image" below](#).

To run a Dockerized load generator:

Run the load generator container using the following command:

```
docker run -id -p <host_port>:54345 performancetesting/microfocus_
oneIlg_windows:<tag version number>
```

Note: Check that the <host_port> on the machine is available and allows incoming requests. You specify this port on the Controller side when connecting to this load generator.

Run a Dockerized load generator using a custom image

If your environment requires customized settings for running the container, you can create a Dockerfile to build a custom image for Docker on Windows.

Examples for custom images:

- To use a specific user account for the processes under which the Vusers are running, to provide support for accessing network resources like script parameter files. After running, the container should be able to verify the user.
- To run Java protocols on Windows load generator containers.
- To define environment variables for proxy server host and port.

To run a custom Dockerized load generator:

1. Create a new folder, and within it create a file named **dockerfile**. Paste the following **FROM** line into the file, using the appropriate LoadRunner Professional version for the **<tag version number>**, and add the relevant customization lines:

```
FROM performancetesting/microfocus_oneIlg_windows:<tag version
number>
```

```
<Customization lines>
```

For customization examples, see ["Examples of customized content for Dockerfiles" below](#)



Tip: For information on commands that can be used in Docker files, see the Docker online documentation.

2. Save the Dockerfile.
3. Open a command line at the **dockerfile** folder path and run the following command, using the name you want for your custom image:

```
docker build -t <custom image name> .
```

4. Create a container for each load generator you want to use, by running the following command (or use any Docker orchestrator tool for running containers):

```
docker run -id -p <host_port>:54345 <custom image name>
```

If the custom image in step 3 was built with a tag then include it in the command:

```
docker run -id -p <host_port>:54345 <custom image name>:<tag version number>
```



Note: Check that the <host_port> on the machine is available and allows incoming requests. You specify this port on the Controller side when connecting to this load generator.

Examples of customized content for Dockerfiles

Example for Vusers under a specified user account

The following gives an example of dockerfile content for running the Vusers under a specified user account with network access to shared locations. Replace the

values between <> with credentials for a valid user account in your environment, with network access to the shared resources.

**Example:**

```
#escape=`
FROM performancetesting/microfocus_one1g_windows:<tag version
number>
RUN c:\LG\launch_service\bin\magentservice.exe -remove
RUN c:\LG\launch_service\bin\magentservice -install
<domain>\<user name> <password>
```

Example for running Java/JMeter/Gatling protocols

The following gives an example of dockerfile content to run Java, JMeter, or Gatling protocols:

**Example:**

```
#escape=`
FROM performancetesting/microfocus_one1g_windows:<tag version
number>
COPY .\<folder contains JDK> <target path in the container>
```

- The path to the target JDK directory defined in the **COPY** line for the **<target path in the container>** must also be added to the **Java VM** runtime settings page:

The screenshot shows the 'Java VM Runtime Settings' dialog box. The 'Virtual Machine' section is active, showing the 'Use the specified JDK' radio button selected with the path 'C:\java\zulux64\'. The 'Additional VM parameters' field is empty. The 'Class Loading' section has the 'Load each Vuser using dedicated class loader' checkbox unchecked. The 'Use Defaults' button is visible in the top right corner.

- For **Java 64-bit protocol** testing, include the following command line in the dockerfile, in order to add the path to the JDK 64-bit **bin** folder to the machine PATH environment variable:

```
RUN powershell [Environment]::SetEnvironmentVariable("\"Path\"",  
$env:Path + "\"<target JDK path in the container>\bin\"",  
[EnvironmentVariableTarget]::Machine)
```

- For **JMeter/Gatling protocol** testing, include the following command line in the dockerfile, in order to add the path for the JDK/JRE to the machine JAVA_HOME environment variable:

```
RUN powershell [Environment]::SetEnvironmentVariable("\"JAVA_<br>HOME\"", "\"<target JDK/JRE path in the container>\"",  
[EnvironmentVariableTarget]::Machine)
```

After running the load generator containers

Add the load generators containers to scenarios. For details, see [Configure Dockerized load generators](#) in the LoadRunner Professional Help Center.


Tips and guidelines

- Dockerized load generators, run from the predefined image, are not supported when running over a firewall.
- Use `docker ps` to list the containers that are running.
- To stop the load generator service:
 - Use `docker stop <load generator container name or ID>` if you want to reuse the same load generator.
 - Use `docker rm -f <load generator container name or ID>` in order to remove the load generator container.
- To access the host network directly, use `--net=host` in place of `-p <host_port>:54345`. We recommend you use this flag if the AUT generates a lot of network activity.

Installation workflow on Linux

The following diagram shows the primary steps in installing the load generator on a Linux platform using the standard installation program.

For details on deploying a load generator on Linux using a Docker container, see ["Deploy Dockerized load generators on Linux" on page 38](#).



1. Prerequisites

- Make sure that your system meets the requirements, as described in ["System requirements and prerequisites" on page 8](#).
- If you are using a **RHEL 8** operating system: By default, libnsl.so.1 is not installed with RHEL 8.0, so you need to manually install it before installing the load generator, or installation will fail. Install using the package manager: `yum install libnsl.i686`
- If you plan to replay **ODBC Protocol** scripts on the Linux machines: Install unixODBC v.2.3.1 or higher.
- The load generator for this version can be installed over any load generator installation from version 12.56 and later. If load generator version 12.55 or earlier is installed, you must first uninstall it. For details, see ["Uninstall load generator 12.55 or earlier" on page 52](#).

2. Run the setup

- **Wizard installation:** To run the installation using the Setup wizard, see ["Install a load generator on Linux with the Setup wizard" below](#).
- **Silent installation:** To perform a silent installation, see ["Silent load generator installation on Linux" on page 37](#).

3. Configure your environment

After the installation, before you can begin working with the load generator you need to configure your environment. This involves setting the appropriate environment variables, checking access to the load generator, and verifying the installation. See ["Configure the Linux environment" on page 44](#).

Install a load generator on Linux with the Setup wizard

This section describes how to install the load generator on a Linux platform using the Setup wizard.

To install the load generator using the Setup wizard:

1. Switch to super user.
2. If Load Generator version 12.55 or earlier is installed on the machine, you must uninstall it manually. For details, see ["Uninstall load generator 12.55 or earlier" on page 52](#).

If you do not uninstall the load generator, you will get an error during the installation.



Tip: If Load Generator 12.56 or later is installed, the Setup wizard uninstalls it during the installation process, then reinstalls it.

3. Unpack the load generator installation package and open the location of the **.bin** file.

4. Launch the Setup wizard:

For:	Type:
[sh and bash shells]	source ./installer.sh
[csh and tcsh shells]	source ./installer.csh
If the source command is not supported by the current shell, use the "dot" command.	For example: . ./installer.csh

Note: It is recommended that you use the **source** command to run the Setup wizard, as shown above. If you run the Setup wizard without using this command, you must manually set the environment variables for the current shell session. For details, see ["Set the environment variables" on page 45](#).

The Load Generator Setup wizard checks that the required prerequisite software is installed on the computer. If any prerequisite software is missing, a message is displayed, and the Setup wizard aborts. Install the required package. Then rerun the Setup wizard.

5. Follow the online instructions to install the load generator.

During installation, you have the option to install CA and TLS (SSL) certificates for the load generator. For details and requirements for these certificates, see ["Using TLS \(SSL\) certificates with LRP" on page 8](#).

For more help during installation, see ["Troubleshoot the load generator Linux installation" on page 54](#).

Note: The default installation path is: `/opt/MF/MF_LoadGenerator/_MF_LoadGenerator_Installation`

6. Exit super user or switch to another user.

7. Configure your environment as described in ["Configure the Linux environment" on page 44](#).

Silent load generator installation on Linux

This section describes how to perform a silent installation of the load generator on a Linux machine.

To perform a silent installation of the load generator:

1. Switch to super user.
2. If a load generator is installed on the machine, you must first uninstall it, otherwise the silent installation will fail. To uninstall the load generator, see ["Uninstall the load generator from a Linux machine" on page 52](#).
3. Change directory to /<path_to_installer_dvd>/load_generator_linux_x64/.
4. Run the following command to silently install the load generator. You can add installation options as shown in the table below.

```
source ./installer.sh -i silent
```

Installation option	Possible values	Details
-DSTART_PRODUCT_AFTER_INSTALL	Yes, No	Launch the load generator at the end of the installation. Default value: Yes
-DINSTALL_GATLING	Yes, No	Available from version: 2023 R1. Install Gatling on the load generator. Default value: No
-DINSTALL_JMETER	Yes, No	Available from version: 2023 R1. Install JMeter on the load generator. Default value: No



Example: The following command runs a silent installation of a load generator with JMeter. The load generator is not launched at the end of the installation.



```
source ./installer.sh -i silent -DINSTALL_JMETER=Yes -DSTART_PRODUCT_AFTER_INSTALL=No
```



Note: It is recommended that you use a **source** command to perform a silent installation, as shown above. If you perform the installation without using the **source** command, you will need to set up the environmental variables after installing the load generator. For details, see ["Set the environment variables" on page 45](#).

If the **source** command is not supported by the current shell, use the "dot" command. For example: `./installer.sh - i silent`.

If you encounter an error during the installation, see ["Troubleshoot the load generator Linux installation" on page 54](#).

Deploy Dockerized load generators on Linux

This section describes how to run a Dockerized load generator on a Linux distribution.

For supported protocols on Dockerized load generators, see the [Supported Protocols](#) guide.

Prerequisites



Note: The Ubuntu image for the OneLG load generator replaces the previous Ubuntu load generator docker image.

For information on OneLG, see [Load generators](#) in the LoadRunner Professional Help Center.

- Install Docker on the target machine, along with its dependencies, and set up the target machine environment as required. Currently, only the 64-bit version is supported. For installation details, see the Docker online documentation.

- Obtain the predefined load generator Docker image. Two images are available, for Linux-Ubuntu and RHEL.

Pull the image from the relevant page, accessible from the performance testing page (<https://hub.docker.com/u/performancecetesting>) in the Docker hub.

Use one of the following commands and appropriate **<tag version number>**, for example, 20.03:

Linux-Ubuntu

```
docker pull performancecetesting/microfocus_onelg_linux_ubuntu:<tag
version number>
```

RHEL

```
podman pull performancecetesting/load_generator_redhat:<tag version
number>
```

Run a Dockerized load generator using the predefined image

Use the ready-to-use image to run a load generator on Docker for Linux. If you need customization for your container, for example, for proxy servers, see ["Run a Dockerized load generator using a custom image" on page 41](#).

To run the Linux-Ubuntu OneLG image for LoadRunner Professional, the appropriate environment variable must be included in the run command: **ONELG_FLAVOR=1**

From LRP version 2023 R1: The following environment variables are available to enable JMeter and Gatling on the load generator if required:

- ENABLE_JMETER
- ENABLE_GATLING

In LRP version **2023**, JMeter and Gatling are enabled on the load generator by default.

To run a Dockerized load generator:

Run the load generator container using the appropriate command for Linux-Ubuntu or RHEL.

Check that the <host_port> on the Linux machine is available and allows incoming requests. You specify this port on the Controller side when connecting to this load generator.

Linux-Ubuntu

- LRP version **2023**:

```
docker run -id -p <host_port>:54345 -e "ONELG_FLAVOR=1" --net=host
performancetesting/microfocus_onelg_linux_ubuntu:<tag version
number>
```

- From LRP version **2023 R1** (to enable Gatling or JMeter, include the bolded variables):

```
docker run -id -p <host_port>:54345 -e "ONELG_FLAVOR=1" -e
"ENABLE_GATLING=1" -e "ENABLE_JMETER=1" --net=host
performancetesting/microfocus_onelg_linux_ubuntu:<tag version
number>
```

RHEL

- LRP version **2023**:

```
podman run -id -p <host_port>:54345 performancetesting/load_
generator_redhat:<tag version number>
```

- From LRP version **2023 R1** (to enable Gatling or JMeter, include the bolded variables):

```
podman run -id -p <host_port>:54345 -e "ENABLE_GATLING=1" -e
"ENABLE_JMETER=1" performancetesting/load_generator_redhat:<tag
version number>
```


Example using SSH

The following gives a simple C# code example for running multiple load generator containers using SSH. There are container orchestrator tools which do the same, for example, Kubernetes, OpenShift, Docker Swarm.

```
using (var client = new SshClient(dockerHost, dockerHostUserName,
dockerHostPasswd))
{
    client.Connect();
    for (int i = 0; i < numOfContainers; i++)
    {
        string command = "docker run -id -p " + lgInitialPort + i) +
":54345 -e "ONELG_FLAVOR=1" --net=host
performancetesting/microfocus_onelg_linux_ubuntu:<tag version
number>";
        var terminal = client.RunCommand(command);
        if (terminal.ExistStatus != 0)
        {
            throw new Exception("Failed to create new Docker container");
        }
        Console.WriteLine("Docker LG with external port" + lgInitialPort +
i + "created.");
    }
    client.Disconnect();
}
```

Run a Dockerized load generator using a custom image

If your environment requires customized settings for running the container, for example for proxy servers, you can follow the procedure below to create a Dockerfile to build a custom image.

Alternatively, you can do the following: Start the container; once it is running, set up the load generator environment variables, then start the load generator manually inside the container.

To create a Dockerfile to run a custom Dockerized load generator:

1. Create a new folder, and within it create a file named **dockerfile**. Paste the **FROM** line, plus the required customization lines, into the file, using the appropriate LoadRunner Professional version for the <tag version number>.

For example, for Linux-Ubuntu:

```
FROM performancetesting/microfocus_onelg_linux_ubuntu:<tag
version number>
ENV http_proxy http://my_proxy_name:port
```

Note: The above customization example is for a proxy. It defines an environment variable for the proxy server host and port in the target image.

2. Save dockerfile.
3. Open a command line at the dockerfile folder path and run the following command, using the name you want for your custom image:

Linux-Ubuntu:

```
docker build -t <custom image name> .
```

RHEL:

```
podman build -t <custom image name> .
```

4. Create a container for each load generator you want to use, by running the following command:

Linux-Ubuntu:

```
docker run -id -p <host_port>:54345 -e "ONELG_FLAVOR=1" --
net=host <custom image name>
```

RHEL:

```
podman run -id -p <host_port>:54345 <custom image name>
```

If the custom image in step 3 was built with a tag then include it in the command, for example:

```
docker run -id -p <host_port>:54345 -e "ONELG_FLAVOR=1" --  
net=host <custom image name>:<tag version number>
```

Note: Check that the <host_port> on the Linux machine is available and allows incoming requests. You specify this port on the Controller side when connecting to this load generator.

After running the load generator containers

Add the load generators containers to scenarios. For details, see [Configure Dockerized load generators](#) in the LoadRunner Professional Help Center.

Tips and guidelines

- Dockerized load generators that are run from the predefined image are not supported when running over a firewall. (Workaround for advanced users: You can develop your own Docker image with MI Listener support.)
- Use `docker ps` to list the containers that are running.
- To stop the load generator service:
 - Use `docker stop <load generator container name or ID>` if you want to reuse the same load generator.
 - Use `docker rm -f <load generator container name or ID>` in order to remove the load generator container.
- The Dockerfile container has an ENTRYPOINT section. The container first runs the commands in ENTRYPOINT. It sets up the environment and then starts the load generator. The command uses a While loop to wait for input, in order to keep the container from exiting. This behavior prevents you from accessing the container while it is running. Make sure to add `-i` while starting the container; otherwise the While loop will consume an excessive amount of CPU.
- If you need entry into the container, add an argument such as `--entrypoint=/bin/bash` when starting the container. After entering the

container, set the load generator environments and start the load generator . You can then switch to the host using CTRL+p and CTRL+q while keeping the container running in the background. To access the container again, use the `docker attach container_id` command.

- To access the host network directly, use `--net=host` in place of `-p <host_port>:54345`. We recommend you use this flag if the AUT generates a lot of network activity.

Configure the Linux environment

This section describes the configuration steps you need to complete after installing the load generator, before you can begin working with the load generator.

To complete the setup process after installing the load generator:

1. Set the appropriate environment variables.

See ["Set the environment variables" on the next page](#).

Note: If you used a **source** command to install the load generator, the Setup wizard automatically sets the appropriate environment variables, and there is no need to perform this step.

2. Verify the load generator installation.

See ["Verify the Linux installation" on page 46](#).

3. Start the load generator.

```
.cd /opt/MF/MF_LoadGenerator/;source env.csh;cd bin;./m_daemon_
setup -install
```

4. Check that Controller is able to access the load generator.

For details, see ["Check Controller connection" on page 48](#).

Set the environment variables

Note: This topic is applicable only if you ran the load generator Setup wizard without using a **source** (or "dot") command. If you used these commands, there is no need to perform any of the procedures described below.

To enable the load generator to run, the following environment variables must be defined:

- **M_LROOT.** The location of the Linux load generator root folder.
- **PATH.** The location of the Linux load generator **bin** directory.
- **PRODUCT_DIR.** The location of the Linux load generator root folder.

The Load Generator Setup wizard performs the following tasks relating to the environment variables:

- Adds the environment variable definitions to the system-wide startup scripts.

If the variable definitions were not correctly set during the setup, see ["Troubleshoot the load generator Linux installation" on page 54](#) for possible solutions.

- Sets environment variables for the current shell session if the **source** command was used to run the Setup wizard.

This topic describes how to set the environment variables for the current shell session if a **source** command was not used to run the Setup wizard.

To determine if environment variables are set, run **verify_generator** (see ["Run verify_generator" on page 47](#)) or use the following command:

```
echo $M_LROOT
```

If the name of the load generator root folder is returned, then the environment variables are correctly set for current shell. If the name of the load generator root folder is not returned, then manually set the variables as described below.

To manually set the environment variables for the current shell session (if the **source** command was not used to run the Setup wizard), execute one of the following commands:

- Bash users:

```
source <load generator root>/env.sh
```

- C Shell users:

```
source <load generator root>/env.csh
```

Verify the Linux installation

The load generator installation includes a setup verification utility, **verify_generator**, that checks the load generator setup on your Linux machine. The verification utility checks environment variables and your startup scripts (**/etc/csh.cshrc**, **\${HOME}/.cshrc** or **/etc/profile**, **\${HOME}/.profile**) to verify that they are set up correctly.

It is strongly recommended that you run **verify_generator** after installing the load generator, before attempting to invoke the load generator. For details on how to run the **verify_generator** utility, see ["Run verify_generator" on the next page](#).

The **verify_generator** utility checks the following:

- All the prerequisite software is installed. (This check is performed for 64-bit installations only.)
- There are at least 128 file descriptors
- The **.rhosts** permissions have been defined properly: **-rw-r--r--**
- The host can be contacted by using **rsh** to the host. If not, it checks for the host name in **.rhosts**
- **M_LROOT** is defined
- **.cshrc** or **.profile** defines the correct **M_LROOT**
- **/etc/csh.cshrc**, **\${HOME}/.cshrc** or **/etc/profile**, **\${HOME}/.profile** defines the correct **M_LROOT**
- **.cshrc** or **.profile** exists in the home directory

- The current user is the owner of the **.cshrc** or **.profile**
- A Linux load generator installation exists in **\$M_LROOT**
- The executables have executable permissions
- PATH contains **\$M_LROOT/bin** and **/usr/bin**

Run verify_generator

It is recommended that you run the **verify_generator** utility after installing the load generator, before attempting to invoke the load generator. For details on what is checked by the **verify_generator** utility, see ["Verify the Linux installation" on the previous page](#).

Note:

- To run this command, you must be a "normal" user and not root user.
- Before you run the **verify_generator** utility, make sure that you have set the DISPLAY environment variable on your machine.

To run verify_generator:

1. From the **<load generator root>/bin** folder, run the following command:

```
./verify_generator
```

For example:

```
/opt/MF/MF_LoadGenerator/bin/verify_generator
```

If you want to receive detailed information about the checks, you can use the **-v** option, as follows:

```
./verify_generator -v
```

2. View the results.
 - If the settings are correct, **verify_generator** returns **OK**.
 - If any of the settings are incorrect, **verify_generator** returns **Failed**, and suggestions on how to correct the setup.

Check Controller connection

If Controller is to connect remotely to the load generator using **rsh** (remote shell), you need to make sure that the load generator can be remotely accessed by Controller.

1. On the load generator machine, locate the **.rhosts** file which is located in the user home directory.
2. In the **.rhosts** file, verify that Controller is included in the list of machines. If it is not listed, add it to the list.

If Controller still cannot connect to the load generator, contact your system administrator.

Connecting to a Linux load generator without using rsh

You can configure Controller to connect to the load generator without using **rsh**. In this case, you need to activate the agent daemon on the load generator, as described below.

This section describes how to connect to a Linux load generator without using **rsh**.

1. On the Linux load generator, run the agent daemon by entering the following command from **<load generator root>/bin**:

```
./m_daemon_setup -install
```

This runs a daemon called **m_agent_daemon**, and if successful, you receive a message: **m_agent_daemon <process ID>**.

The agent now keeps running, even if the user is logged off. You can stop the agent by using the command explained in step 9 below, or by rebooting the machine.

Note: If you look at the **m_agent_daemon[xxx].log** log file in the temp directory, you may see communication errors, even if the installation succeeded.

2. In Controller, select **Scenario > Load Generators**. The Load Generators dialog box opens.
3. Click **Add**. The Add New Load Generator dialog box opens.
4. In the **Name** box, enter the name of the computer on which the load generator is running.
5. From the **Platform** list, select **Linux**.
6. Click **More**.
7. Click the **Linux Environment** tab, and make sure that the **Don't use RSH** check box is selected.
8. Connect as usual.
9. To stop the agent daemon, run the following command from the **<LoadRunner Professional root>/bin** directory:

```
./m_daemon_setup -remove
```

This stops the **m_agent_daemon** daemon, and if successful, you receive the message: **m_agent_daemon is down**.

Improve load generator performance

This section includes recommendations for improving load generator performance. You can increase the number of file descriptors, process entries, and amount of swap space by configuring the kernel.

Note: Most operating systems using the Linux load generator have sufficient default file descriptors, process entries, and swap space, and rarely require reconfiguration.

This section includes:

- ["Increase file descriptors" on the next page](#)
- ["Increase process entries" on page 51](#)

- ["Increase swap space " on the next page](#)

Increase file descriptors

A load generator uses the following file descriptor resources:

- 14 file descriptors for the launch service
- 20 file descriptors for the agent
- 30 file descriptors for each Vuser driver. By default, there is a driver for every 50 Vusers.
- File descriptors for the running Vusers. Each Vuser requires two descriptors.

For example, to compute the number of file descriptors used in running 100 threaded Vusers, the load generator requires:

Descriptors	Purpose of the descriptors
14	For the launcher
20	For the agent
60	For 2 drivers (30 x 2, each one drives 50 Vusers)
200	For 100 Vusers (each Vuser requires 2)

Total: 294 file descriptors

If Vusers are run as processes instead of threads, one driver is run per Vuser. Therefore, each Vuser requires 30 file descriptors.

The procedure to increase the number of file descriptors differs between shells.

In the examples below, the number of descriptors is increased to the maximum of 1024.

- For sh and ksh users, type:

```
ulimit -n 1024
```

- For csh users, type:

```
limit descriptors 1024
```

Below is an alternate procedure to increase file descriptors. In this example, the number of descriptors is increased to the maximum of 8192.

1. Add the following line to the **/etc/security/limits.conf** file:

```
hard nfile 8192
```

2. Add the following line to the **/etc/sysctl.conf** file:

```
fs.file-max = 8192
```

3. Reboot the machine.

Increase process entries

Each Vuser requires several free process entries. To increase the number of process entries on your system, you must reconfigure the kernel.

This section describes how to reconfigure the kernel for Linux platforms.

1. Locate the **/etc/security/limits.conf** file.
2. Set the maximum number of processes in the limits file. Type:

```
hard nproc 8192
```

3. Reboot the machine.

Increase swap space

Each Vuser requires swap space ranging in size from 200 KB to 4 MB. Before adding space to your system configuration, you should determine your paging requirements. For environments running programs with very large memory requirements, it is recommended to have paging space of four times the physical memory. If you do not have enough paging space, certain processes may be killed, and others will be unable to start.

Uninstall the load generator from a Linux machine

This section describes how to uninstall the load generator from a Linux machine.

This section includes:

- ["Uninstall load generator 12.55 or earlier" below](#)
- ["Uninstall load generator 12.56 or later" on the next page](#)

Uninstall load generator 12.55 or earlier

You can uninstall load generator 12.55 or earlier versions using a manual command or silently.

To uninstall load generator version 12.55 or earlier:

1. Make sure that you are logged in as the same user who installed the load generator.
2. Make sure that the **m_agent_daemon** process is not running on the machine. If it is running, kill its process:

```
cd /opt/HP/HP_LoadGenerator/bin;./m_daemon_setup -kill;su -;
```

3. Change the current directory to the installation directory:

```
cd <path_to_installation_folder>/_HP_LoadGenerator_Installation
```

4. Switch to super user.
5. Uninstall the load generator:

- **Manual uninstall:** run the following command:

```
sh ./Change_HP_LoadGenerator_Installation
```

- **Silent uninstall:** Run the following command:

```
sh ./Change_HP_LoadGenerator_Installation -i silent
```

Uninstall load generator 12.56 or later

You can uninstall load generator 12.56 or later using the Setup wizard or a manual command, or silently.

To uninstall load generator version 12.56 or later:

1. Make sure that you are logged in as the same user who installed the load generator.
2. Make sure that the **m_agent_daemon** process is not running on the machine. If it is running, kill its process:

```
cd /opt/MF/MF_LoadGenerator/bin;./m_daemon_setup -kill;su -;
```

3. Change the current directory to the installation directory:

```
cd <path_to_installation_folder>/_MF_LoadGenerator_Installation
```

4. Switch to super user.
5. Uninstall the load generator:

- **Manual uninstall:** Run the following command:

```
sh ./Change_MF_LoadGenerator_Installation
```

- **Silent uninstall:** Run the following command:

```
sh ./Change_MF_LoadGenerator_Installation -i silent
```

Troubleshoot the load generator Linux installation

This section describes troubleshooting tasks relating to the setup of the Linux load generator.

This section includes:

- ["Environment variables were not set correctly in the system-wide startup scripts" below](#)
- ["Error when installing the load generator on a Linux platform" on page 58](#)
- ["Environment variables are not unset after uninstalling the load generator" on page 58](#)
- ["Unable to run Vusers on the load generator" on page 59](#)

Environment variables were not set correctly in the system-wide startup scripts

To enable the load generator to run, the system-wide startup scripts must be modified to set specific environment variables. The required modifications to the startup scripts are made by the Load Generator Setup wizard. If the startup scripts were not correctly modified during the setup of the load generator, you can manually make the required changes to the startup scripts as described below. The required changes differ slightly between C shell users, and Bourne and Korn shell users.

- **Manually modifying the startup scripts for C shell users**

During the load generator installation process, the wizard creates the **env.csh** script. This script includes the commands to set the required environment variables for C shell users. A sample **env.csh** script is shown below.

```
setenv PRODUCT_DIR <Load Generator installation directory>
setenv M_LROOT ${PRODUCT_DIR}
```

```
if ( ! $?PATH ) then
    setenv PATH ""
endif
setenv PATH ${M_LROOT}/bin:${PATH}"
```

Add the following line to the **/etc/csh.cshrc** or **~/.cshrc** startup script to execute the **env.csh** script during the shell startup:

```
source <Load Generator installation directory>/env.csh
```

For example:

```
source /opt/MF/MF_LoadGenerator/env.csh
```

The effect of making the above modification to the startup script is similar to the modifications that are made by the Setup wizard. A sample of the modifications that the Setup wizard makes to the **/etc/csh.cshrc** startup script is shown below:

```
# New environment setting added by MF_LoadGenerator on Wed Jan 30
16:20:10 IST 2020 2.

# The unmodified version of this file is saved in
/etc/.login1557000131.

# Do NOT modify these lines; they are used to uninstall.

setenv PRODUCT_DIR "/opt/MF/MF_LoadGenerator"

# End comments by InstallAnywhere on Wed Jan 30 16:20:10 IST 2020
2.

# New environment setting added by MF_LoadGenerator on Wed Jan 30
16:20:10 IST 2020 5.

# The unmodified version of this file is saved in
/etc/.login1557000131.

# Do NOT modify these lines; they are used to uninstall.
```

```
setenv M_LRROOT "/opt/MF/MF_LoadGenerator"

# End comments by InstallAnywhere on Wed Jan 30 16:20:10 IST 2020
5.

# New environment setting added by MF_LoadGenerator on Wed Jan 30
16:20:10 IST 2020 8.

# The unmodified version of this file is saved in
/etc/.login1557000131.

# Do NOT modify these lines; they are used to uninstall.

if ( ! $?PATH ) then

setenv PATH ""

endif

setenv PATH "/opt/MF/MF_LoadGenerator/bin:${PATH}"

# End comments by InstallAnywhere on Wed Jan 30 16:20:10 IST 2020
8.
```

- **Manually modifying the startup scripts for Bourne and Korn shell users**

During the load generator installation, the Setup wizard creates the **env.sh** script. This script includes commands to set the required environment variables for Bourne shell and Korn shell users.

Add the following line to the **/etc/profile** or **~/.profile** startup script to execute the **env.sh** script during the shell startup:

```
source <Load Generator installation directory>/env.sh
```

For example:

```
source /opt/MF/MF_LoadGenerator/env.sh
```

The effect of making the above modification to the startup script is similar to the modifications that are made by the Setup wizard. A sample of the modifications that the Setup wizard makes to the **/etc/profile** startup script is shown below:


```
# New environment setting added by MF_LoadGenerator on Fri Jan 16
11:14:24 IST 2020 1.

# The unmodified version of this file is saved in
/etc/profile1806316421.

# Do NOT modify these lines; they are used to uninstall.
PRODUCT_DIR=/opt/MF/MF_LoadGenerator

export PRODUCT_DIR

# End comments by InstallAnywhere on Fri Jan 16 11:14:24 IST 2020
1.

# New environment setting added by MF_LoadGenerator on Fri Jan 16
11:14:24 IST 2020 4.

# The unmodified version of this file is saved in
/etc/profile1806316421.

# Do NOT modify these lines; they are used to uninstall.
M_LROOT=/opt/MF/MF_LoadGenerator

export M_LROOT

# End comments by InstallAnywhere on Fri Jan 16 11:14:24 IST 2020
4.

# New environment setting added by MF_LoadGenerator on Fri Jan 16
11:14:24 IST 2020 7.

# The unmodified version of this file is saved in
/etc/profile1806316421.

# Do NOT modify these lines; they are used to uninstall.
PATH="/opt/MF/MF_LoadGenerator/bin:${PATH}"

export PATH

# End comments by InstallAnywhere on Fri Jan 16 11:14:24 IST 2020
7. LoadRunner settings #PATH=${M_LROOT}/bin:$PATH; export PATH
```

Error when installing the load generator on a Linux platform

When you use the **source installer.sh** command to install the latest load generator version on a Linux machine on which a load generator was previously installed, you may receive the following error message:

"An error occurred while trying to manage the selected instance."

Solution:

1. Open the registry file **/var/.com.zerog.registry.xml** and locate the element **"product"** with attribute **"name"="MF_LoadGenerator"**.

For example:

```
<product name="MF_LoadGenerator" id="77f695c1-1f0c-11b2-883d-c486a85f6555" version="20.00.0.0" copyright="2019" info_url="http://www.microfocus.com" support_url="http://www.microfocus.com" location="/opt/MF/MF_LoadGenerator" last_modified="2019-11-21 13:12:14">
```

2. Record the value of the **"location"** attribute.
3. Remove the entire directory that is referred to by the **"location"** attribute.
4. Delete the registry file **/var/.com.zerog.registry.xml**.
5. Rerun the **source installer.sh** command.

Environment variables are not unset after uninstalling the load generator

When you uninstalled the Linux load generator, the Setup wizard might not have unset the load generator environment variables (M_LROOT, PRODUCT_DIR, and PATH) for the current shell. To unset the environment variables, close the current shell session and invoke a new one, or manually unset the variables as described below:

- To unset the M_LROOT and PRODUCT_DIR variables:
 - [bash shells] Use the **unset** command.
 - [csh shells] Use the **unsetenv** command.

- To update the PATH variable to exclude the load generator binary directory, type:
 - [bash shells] `PATH=<required list of paths>; export PATH`
 - [csh shells] `setenv PATH <required list of paths>`

Unable to run Vusers on the load generator

If you are unable to run Vusers on the load generator, no specific error is reported, and the Vuser protocol requires a third-party application or client to be present on load generator side, check the dynamic libraries used by the application. This enables you to establish if any shared objects cannot be found. A shared object that cannot be found may indicate either a missing prerequisite package or an environment variable issue.

To check the dynamic libraries used by an application, type:

```
ldd application_name
```

For example, type `ldd mdrv` to determine if all the dependencies of the **mdrv** executable can be found. If any dependencies are not found, run **verify_generator** as described in ["Run verify_generator" on page 47](#).

Note: If you are running Vusers for a protocol that requires a client installation (for example, Oracle), make sure that the path for the client libraries is included in the dynamic library path environment variable (LD_LIBRARY_PATH or SHLIB_PATH).

Installing the LoadRunner Data Hub and Web Connector

The LoadRunner Data Hub is a communication channel based on Kafka technology that enables more robust communication between LoadRunner components. To use this channel, install the Data Hub. In addition, if your LoadRunner components communicate via the web (for example, if a load generator is behind a firewall and communicates via a proxy), you need to install the Data Hub Web Connector.

The Data Hub and Web Connector must be installed on Linux. They can communicate with LoadRunner components running on Linux and Windows machines.

After you install the Data Hub and Web Connector (if necessary), you need to configure the LoadRunner components to use them. For details, see [Data Hub and Web Connector setup](#) in the LoadRunner Professional Help Center.

This chapter includes:

- [Data Hub installation](#) 60
- [Web Connector installation](#) 64

Data Hub installation

Follow these primary steps to install the Data Hub:

1. Prerequisites

- Make sure that your system meets the requirements, as detailed in the [Support Matrix](#).
- The Data Hub requires the latest version of Java JRE to be installed.

2. Download the installation package

Download the Data Hub installation package from [AppDelivery Marketplace](#).

3. Run the setup

- **Wizard installation:** To run the installation using the Data Hub Setup wizard, see "[Install the Data Hub with the Setup wizard](#)" on the next page.

- **Silent installation:** To perform a silent installation, see ["Install the Data Hub silently" below](#).

4. **Verify the installation**

See ["Verify the Data Hub installation" on page 64](#).

Install the Data Hub with the Setup wizard

This section describes how to install the LoadRunner Data Hub using the Setup wizard.

To install the Data Hub using the Setup wizard:

1. Switch to super user.
2. Unpack the Data Hub installation package and open the location of the **.bin** file.
3. Launch the Setup wizard: For [sh and bash shells], type `./inst64.bin`
4. Follow the online instructions to install the Data Hub.

The default installation path is: **`/opt/MF/MF_LoadRunner_Data_Hub/_MF_LoadRunner_Data_Hub_Installation`**

During installation, you have the option to install CA and TLS (SSL) certificates. For details and requirements for these certificates, see ["Using TLS \(SSL\) certificates with LRP" on page 8](#).

5. Exit super user or switch to another user.

Install the Data Hub silently

This section describes how to perform a silent installation of the Data Hub.

This section includes:

- ["Run a silent installation" on the next page](#)
- ["Silent installation options" on page 63](#)

Run a silent installation

You can install the Data Hub silently by following the steps below.

To perform a silent installation of the Data Hub:

1. Switch to super user.
2. Unpack the Data Hub installation package.
3. Create a file named **installer.properties** using the following template, changing the parameters as needed.

Tip: An **installer.properties** file is generated when you run the Setup wizard, and can be used again for later silent installations.

```
#Choose Install Folder
#-----
USER_INSTALL_DIR=/opt/MF/MF_LoadRunner_Data_Hub

#Choose Link Location
#-----
USER_SHORTCUTS=/usr/local/bin/MF/MF_LoadRunner_Data_Hub

#Install
#-----
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub/_MF_LoadRunner_
Data_Hub_Installation/Change_MF_LoadRunner_Data_Hub_
Installation.lax=Yes
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_
Hub/zookeeper.service=Yes
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub/kafka.service=Yes
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub/run_after_
install.sh=Yes

#Install certificate
#-----
```

```
INSTALL_CERTIFICATE=\\", \\No\"
```

4. Save the **installer.properties** file in the same location as the installer file.
5. Run the installation command using the following syntax:

```
./inst64.bin [-f<path to installer properties file> | -options]
```

You can modify the installation by adding options to this command. For details, see "[Silent installation options](#)" below.

Note:

- When the **installer.properties** file is saved in the same directory as the installer, it overrides all other command line options unless the **-f** option is used to specify another valid properties file.
- The path to the installer properties file may be either absolute, or relative to the directory in which the installer resides.

For example, the following command installs the Data Hub silently using an **installer.properties** file that is saved in the same location as the installer:



Example: `./inst64.bin -i silent`

Silent installation options

You can add the following options to the silent installation command:

Option	Description
<code>-i [swing console silent]</code>	Specifies the user interface mode for the installer.
<code>-D<name>=<value></code>	Specifies the installer properties.
<code>-r <path to generate response file></code>	Generates a response file.

Repair and uninstall options

The following options can be used to repair or uninstall the Data Hub:

Option	Description
-repair	Repairs the installation.
-uninstall	Uninstalls the Data Hub.

Verify the Data Hub installation

To verify that the Data Hub was installed successfully, run the following commands to check the status of zookeeper and kafka services. If these services are running, the installation was successful.

```
service zookeeper status
```

```
service kafka status
```

Web Connector installation

Follow these primary steps to install the Web Connector using the standard installation program:

1. Review the system requirements

Before you install the Web Connector, make sure that your system meets the requirements, as detailed in the [Support Matrix](#).

2. Download the installation package

The Web Connector installation package is included in the Data Hub installation package. If you have not already downloaded the Data Hub installation package, download it from [AppDelivery Marketplace](#).

3. Run the setup

- **Wizard installation:** To run the installation using the Web Connector Setup wizard, see "[Install the Web Connector with the Setup wizard](#)" on the next [page](#).

- **Silent installation:** To perform a silent installation, see ["Install the Web Connector silently" below](#).

4. **Verify the installation**

See ["Verify the Web Connector installation" on page 68](#).

Install the Web Connector with the Setup wizard

This section describes how to install the Web Connector using the Setup wizard.

To install the Web Connector using the Setup wizard:

1. Switch to super user.
2. Unpack the Web Connector installation package and open the location of the .bin file.
3. Launch the Setup wizard: For [sh and bash shells], type `./inst64.bin`
4. Follow the online instructions to install the Web Connector.

The default installation path is: **`/opt/MF/MF_LoadRunner_Data_Hub_Web_Connector/_MF_LoadRunner_Data_Hub_Web_Connector_Installation`**

During installation, you have the option to install CA and TLS (SSL) certificates.

For details and requirements for these certificates, see ["Using TLS \(SSL\) certificates with LRP" on page 8](#).

5. Exit super user or switch to another user.

Install the Web Connector silently

This section describes how to perform a silent installation of the Web Connector.

This section includes:

- ["Run a silent installation" on the next page](#)
- ["Silent installation options" on page 67](#)

Run a silent installation

You can install the Web Connector silently by following the steps below.

To perform a silent installation of the Web Connector:

1. Switch to super user.
2. Unpack the Web Connector installation package.
3. Create a file named **installer.properties** using the following template, changing the parameters as needed. The template here installs the Web Connector with the default LoadRunner certificates.

Tip: An **installer.properties** file is generated when you run the Setup wizard, and can be used again for later silent installations.

```
#Choose Install Folder
#-----
USER_INSTALL_DIR=/opt/MF/MF_LoadRunner_Data_Hub_Web_Connector
#Choose Link Location
#-----
USER_SHORTCUTS=/usr/local/bin/MF/MF_LoadRunner_Data_Hub_Web_
Connector
#Install
#-----
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub_Web_Connector/_MF_
LoadRunner_Data_Hub_Web_Connector_Installation/Change_MF_
LoadRunner_Data_Hub_Web_Connector_Installation.lax=Yes
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub_Web_
Connector/webconnector.service=Yes
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub_Web_Connector/run_
after_install.sh=Yes
-fileOverwrite_/opt/MF/MF_LoadRunner_Data_Hub_Web_
Connector/webconnector.sh=Yes
#Install certificate
#-----
INSTALL_CERTIFICATE="\\", \"No\""
```

4. Save the **installer.properties** file in the same location as the installer file.
5. Run the installation command using the following syntax:

```
./inst64.bin [-f<path to installer properties file> | -options]
```

You can modify the installation by adding options to this command. For details, see ["Silent installation options" below](#).

Note:

- When the **installer.properties** file is saved in the same directory as the installer, it overrides all other command line options unless the **-f** option is used to specify another valid properties file.
- The path to the installer properties file may be either absolute, or relative to the directory in which the installer resides.

For example, the following command installs the Web Connector silently using an **installer.properties** file that is saved in the same location as the installer:



Example: `./inst64.bin -i silent`

Silent installation options

You can add the following options to the silent installation command:

Option	Description
-i [swing console silent]	Specifies the user interface mode for the installer.
-D<name>=<value>	Specifies the installer properties.
-r <path to generate response file>	Generates a response file.

The following options can be used to repair or uninstall the Web Connector:

Option	Description
-repair	Repairs the installation.
-uninstall	Uninstalls the Web Connector.

Verify the Web Connector installation

To verify that the Web Connector was installed successfully, run the following command to check the status of the webconnector service. If this service is running, the installation was successful.

```
service webconnector status
```